

Automation Command Reference Manual

for

WaveRunner Oscilloscopes



LeCroy Corporation

700 Chestnut Ridge Road Chestnut Ridge, NY, 10977-6499 Tel: (845) 578-6020, Fax: (845) 578 5985

Internet: www.lecroy.com

© 2010 by LeCroy Corporation. All rights reserved.

LeCroy and other product or brand names are trademarks or requested trademarks of their respective holders. Information in this publication supersedes all earlier versions. Specifications are subject to change without notice.

918500 RevA

AUTOMATION COMMAND REFERENCE MANUAL - INTRODUCTION

Introduction

This manual provides a comprehensive reference of all the commands available to a controlling application when using WaveRunner oscilloscopes. Automation enables the controlling application to run on the instrument itself.

PLEASE NOTE THE FOLLOWING:

- Available commands include ones for purchased options you may or may not have on your oscilloscope. For more information, contact your local LeCroy sales office for more information about options available for your instrument.
- While we encourage the use of our code examples provided in our manuals, cutting and pasting code samples
 directly from this .pdf manual into scripts cause syntax errors (typically illegal ASCII quotation characters). Carefully
 review code sample formatting during reuse.

The information in this manual is split into **Control** and **Processor** sections, each with their own table of contents.

app	
app.Acquisition	
app.Acquisition.AuxOutput	
app.Acquisition.Channels	
app.Acquisition.Cx	
app.Acquisition.Cx.Out.Result	
app.Acquisition.Horizontal	
app.Acquisition.Trigger	
app.Acquisition.Trigger.Cx	
app.Acquisition.Trigger.Digital	
app.Acquisition.Trigger.Ext	
app.Acquisition.Trigger.Serial	
app.Acquisition.Trigger.Serial.I2C	
app.Acquisition.Trigger.Serial.Protocol (Standard = "CAN")	
app.Acquisition.Trigger.Serial.Protocol (Standard = "FLX")	
app.Acquisition.Trigger.Serial.Protocol (Standard = "I2C")	
app.Acquisition.Trigger.Serial.Protocol (Standard = "I2S")	
app.Acquisition.Trigger.Serial.Protocol (Standard = "LIN")	
app.Acquisition.Trigger.Serial.Protocol (Standard = "MIL1553")	
app.Acquisition.Trigger.Serial.Protocol (Standard = "RS232")	
app.Acquisition.Trigger.Serial.Protocol (Standard = "SPI")	
app.Acquisition.Trigger.Serial.Protocol (Standard = "UART")	
app.Cursors	
app.Display	
app.ElectricalTelecom	
app.ElectricalTelecom.ET	
app.ElectricalTelecom.ET.Out.Result	
app.HardCopy	
app.LabNotebook	
app.LogicAnalyzer	
app.LogicAnalyzer.Digitalx	
app.LogicAnalyzer.Digitalx.Out.Result	
app.LogicAnalyzer.Trigger	
app.Math	
app.Math.Functions	
app.Math.Fx	
ann Math Ex Operator1Setup	

app.Math.Fx.Out.Result	
app.Math.Fx.Zoom	
app.Math.XY	
app.Math.XY.Out.Result	
app.Measure	
app.Measure.Measure	
app.Measure.PRemote.histo.Result	
app.Measure.PRemote.last.Result	
app.Measure.PRemote.max.Result	
app.Measure.PRemote.mean.Result	
app.Measure.PRemote.min.Result	
app.Measure.PRemote.num.Result	
app.Measure.PRemote.sdev.Result	
app.Measure.PRemote.Statistics	
app.Measure.Px	
app.Measure.Px.histo.Result	
app.Measure.Px.last.Result	
app.Measure.Px.max.Result	
app.Measure.Px.mean.Result	
app.Measure.Px.min.Result	
app.Measure.Px.num.Result	
app.Measure.Px.Operator	
app.Measure.Px.Out.Result	
app.Measure.Px.sdev.Result	
app.Measure.Px.Statistics	
app.Memory	
app.Memory.Memories	
app.Memory.Mx	
app.Memory.Mx.Out.Result	
app.Memory.Mx.Zoom	
app.PassFail	
app.PassFail.LastPass.Result	
app.PassFail.NumPassed.Result	
app.PassFail.Qx	
app.PassFail.Qx.Out.Result	
app.PassFail.Rate.Result	
ann PassFail Tests Result	

app.Preferences	1-170
app.Preferences.EMail	1-172
app.RecallSetupLock	1-173
app.SaveRecall	1-173
app.SaveRecall.Setup	1-174
app.SaveRecall.Table	1-178
app.SaveRecall.Utilities	1-179
app.SaveRecall.Waveform	1-180
app.SDA	1-18
app.SDA.BadBits	1-200
app.SDA.BadBits.Out.Result	1-208
app.SDA.Bits	1-208
app.SDA.Bits.Out.Result	1-210
app.SDA.Eye	1-210
app.SDA.Eye.Out.Result	1-213
app.SDA.FindFreqReference	1-213
app.SDA.FindFreqReference.Out.Result	1-213
app.SDA.FindFreqStream	1-213
app.SDA.FindFreqStream.Out.Result	1-214
app.SDA.FindLevelReference	1-214
app.SDA.FindLevelReference.Out.Result	1-21
app.SDA.FindLevelStream	1-21
app.SDA.FindLevelStream.Out.Result	1-21
app.SDA.Mask2Hits	1-21
app.SDA.Mask2Hits.Out.Result	1-21
app.SDA.Mask2Out	1-21
app.SDA.Mask2Out.Out.Result	1-21
app.SDA.MaskHits	1-216
app.SDA.MaskHits.Out.Result	1-216
app.SDA.MaskOut	1-216
app.SDA.MaskOut.Out.Result	1-21
app.SDA.PRBS	1-21
app.SDA.PRBS.Out.Result	1-220
app.SDA.SDAStatus	1-22
app.SDA.TIE	1-22
app.SDA.TIE.Out.Result	1-22
app.SDA.TIEF	1-22

app.SDA.TIEF.Out.Result	1-2
app.SerialDecode	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "8B10B")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "Audiol2S")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "AudioLJ")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "AudioRJ")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "AudioTDM")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "CAN")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "CANHL")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "FLX")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "GMCANHL")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "GMCANLAN")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "I2C")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "LIN")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "MIL1553")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "PCIE1X1")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "PCIE1X2")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "PCIE4X1")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "RS232")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "SIOP")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "SPI")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "SPICustom")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "SPIDDR")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "SSPI")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "UART")	1-2
app.SerialDecode.Decode[n].Protocol (Protocol = "USART")	1-2
app.SerialDecode.Decodex	1-2
app.SerialDecode.Decodex.Decode	1-2
app.SerialDecode.Decodex.Out.Result	1-2
app.SerialDecode.FlexRayMeasure	1-2
app.SerialDecode.FLXEye	1-2
app.SerialDecode.FLXEye.Out.Result	1-2
app.SerialDecode.Measure	1-2
app.SpecAnalyzer	1-2
app.SpecAnalyzer.SpecAn	1-2
app.SpecAnalyzer.SpecAn.Out.Result	
ann SnecAnalyzer SnecAnTable	1-3

app.SpecAnalyzer.SpecAnTable.Out.Result	1-294
app.SystemControl	1-294
app.Utility.DateTimeSetup	1-294
app.Utility.Options	1-298
app.Utility.Remote	1-299
app.Utility.Remote.IOManager.CIOPortU3GPIB	1-300
app.Utility.Remote.IOManager.CLSIBPort	1-300
app.WaveScan	1-300
app.WaveScan.ScanDecode	1-301
app.WaveScan.ScanDecode.Out.Result	1-301
app.WaveScan.ScanHisto	1-302
app.WaveScan.ScanHisto.Histogram	1-304
app.WaveScan.ScanHisto.Out.Result	1-306
app.WaveScan.ScanHisto.Zoom	1-306
app.WaveScan.ScanOverlay	1-307
app.WaveScan.ScanOverlay.Out.Result	1-309
app.WebEditor	1-309
app.XPort	1-311
app.Zoom	1-311
app.Zoom.Zx	1-313
app.Zoom.Zx.Out.Result	1-317
app.Zoom.Zx.Zoom	1-317

LECROY.XSTREAMDSO

app

This is the root of the automation hierarchy, all other nodes are accessed from this point.

AutoSetup	Action
ClearSweeps	Action
Exit	Action
FirmwareVersion	String
Height	Property
HideClock	Bool
InstrumentID	String
InstrumentModel	String
Left	Property
Maximize	Action
Minimize	Action
Quit()	Method
ResetPreferences	Action
Restore	Action
SetToDefaultSetup	Action
Shutdown	Action
Sleep([in] double timeoutMilliseconds)	Method
Тор	Property
TouchScreenEnable	Bool
WaitUntilIdle([in] double timeoutSeconds)	Method
Width	Property
Windowed	Action
WindowState	Property

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Popup a dialog containing the instrument model MsgBox "Model is: " & app.InstrumentModel

AutoSetup Action

Description

Starts an AutoSetup operation. When input channels are visible, AutoSetup operates only on those visible channels. If no channels are visible, all channels are affected by AutoSetup. With more than one channel visible, the first visible channel in numerical order, that has a detectable signal applied to it, is automatically set up for edge triggering.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Start an Auto-Setup process.
app.AutoSetup
```

ClearSweeps Action

Description

Clears all accumulated sweeps for all subsystems. These include Channel Pre-Processing, Math, Measure, and Display Persistence. Note that subsystem-specific clear sweeps controls are also available. For the details please refer to the ClearSweeps control for each subsystem.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Clear all accumulated sweeps for all subsystems.
app.ClearSweeps
```

Exit Action

Description

Equivalent to app.Quit() method.

Firmware Version String

Range Any number of characters

Description

Queries the firmware version of the instrument in the form - "1.0.0 (build 12345)"

Example

```
' Microsoft Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Query the firmware version number of the instrument.
MsgBox "Firmware Version is: " + app.FirmwareVersion
```

Height Property

Description

Sets/Queries the height in pixels of the instrument display on the PC screen.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the height of the instrument window to 400 pixels.
app.Height = 400
```

HideClock Book

Description

Hides/Shows the clock that resides in the lower-right corner of the display of the instrument.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Hide the clock for 3 seconds.
app.HideClock = True
app.Sleep(3000)
app.HideClock = False
```

InstrumentID String

Range Any number of characters

Description

Reads the complete ID of the instrument in the format: "LECROY,WM8500,WM000001,0.0.0", which includes the maker, the instrument model number, the serial number, and the version number.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Present the ID of the instrument.
MsgBox app.InstrumentID
```

InstrumentModel String

Range Any number of characters

Description

Queries the model number of the instrument.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Present the model number of the instrument.
MsgBox app.InstrumentModel
```

Left Property

Description

Sets/Queries the position in pixels of the left edge of the instrument display on the PC screen. The position is measured from the left edge of the screen to the left edge of the instrument window.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the position of the left edge of the instrument window to 100 pixels.
app.Left = 100
```

Maximize Action

Description

Maximize the instrument window to fill the underlying desktop. Equivalent to app.WindowState = 1

Minimize Action

Description

Minimizes the instrument window to reveal the underlying desktop. It will display a small window in the bottom right corner of the display, which when clicked will restore the window to full-screen mode. To programmatically restore the window refer to the app.WindowState control.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Minimize the instrument display.
app.Minimize
```

Quit() Method

Description

Closes the instrument application. The instrument will prompt the user with an 'Are you sure?' dialog before closing down. Note that until the user responds to the dialog, control via Automation will be blocked.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Quit the instrument application with a confirmation prompt.
app.Quit
```

ResetPreferences Action

Description

Resets all scope preferences to their default states. The set includes the current remote communications port, the color palette settings, etc. but does not include the main DSO controls such as V/Div, T/Div, etc. These main instrument controls can be reset using the SetToDefaultSetup control.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Reset all instrument preferences.
app.ResetPreferences
```

Restore Action

Description

Restore the instrument display to its position and size before the last minimize request.

SetToDefaultSetup Action

Description

Restores the instrument setup to its default state. Note that certain settings will not be restored to the default state. These are the user preferences, such as the current remote communications port, and the color settings, which may be reset, if required, using the ResetPreferences action.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Restore the instrument to its default state.
app.SetToDefaultSetup
```

Shutdown Action

Description

Shuts down the instrument. It will prompt the user with an 'Are you sure?' dialog before shutting down. Note that until the user responds to the dialog, control via Automation will be blocked.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Shut down the instrument with a confirmation prompt.
app.Shutdown
```

Sleep([in] double timeoutMilliseconds)

Method

Description

Causes the main execution thread of the instrument application to sleep for the specified time period, defined in milliseconds.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
MsgBox "Sleeping for 10 seconds..."
app.Sleep(10000)
MsgBox "Sleep finished"
```

Top Property

Description

Sets/Queries the position in pixels of the top edge of the instrument display on the PC screen. The position is measured downwards from the top of the screen to the top of the instrument window.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the position of the top edge of the instrument window to 100 pixels.
app.Top = 100
```

TouchScreenEnable Book

Description

Sets/Queries the state of the touch-screen enable control. This is equivalent to the front-panel Touch Screen button.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Disable touch-screen if it is enabled.
if app.TouchScreenEnable = True then
    app.TouchScreenEnable = False
End if
```

WaitUntilldle([in] double timeoutSeconds)

Method

Description

Waits until either the application is idle or the specified timeout expires, specified in seconds. This evaluates to True if the application completes before the timeout expires, and to False if a timeout occurs.

When Trigger mode is Auto or Run, the application is never Idle. In this case the call to WaitUntilIdle returns after the next acquisition and any configured processing.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Wait with a timeout of five seconds.
app.WaitUntilIdle(5)
```

Width Property

Description

Sets/Queries the width in pixels of the instrument display on the PC screen.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the width of the instrument window to 800 pixels.
app.Width = 800
```

Windowed Action

Description

Places the instrument application in windowed mode (as opposed to full-screen mode). Places the application in the upper-part of the display screen with a sizable border.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the instrument display into the windowed mode.
app.Windowed
```

WindowState Property

Description

Sets/Queries the state of the PC window used by the instrument display.

- 0 windowed
- 1 full screen
- 2 minimized

Trying to set values greater than 2 or less than 0 will result in the value 0 (windowed) being set.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the instrument window state to windowed.
app.WindowState = 0
```

ACQUISITION app.Acquisition

This group of variables controls the input channels C1, C2, C3 and C4, the timebase, the trigger, and the Aux Output.

Names of the form app. Acquisition. Channels.xxxx are aliases of simpler names which are described in this section of the manual. Examples of alias pairs are as follows -

app.Acquisition.Channels("Cx") is equivalent to app.Acquisition.Cx app.Acquisition.Channels(1) is equivalent to app.Acquisition.C1 app.Acquisition.Channels("Cx").Out.Result is equivalent to app.Acquisition.Cx.Out.Result

Acquire([in] double timeoutSeconds, [in] long bForceTriggerOnTimeout)	Method
Calibrate	Action
CalibrateAll	Action
CalNeeded	Integer
ClearSweeps	Action
HorOffset	Double
TriggerMode	Enum

Acquire([in] double timeoutSeconds, [in] long bForceTriggerOnTimeout)

Method

Description

Action/Query. Takes a single acquisition. The first of the two arguments specifies a timeout; the second, which is optional, specifies whether or not to force a trigger when the timeout occurs. Evaluates to True if a trigger occurred, or False if a timeout occurred.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Start an acquisition, wait for up to 5 seconds for a trigger
' event, force a software trigger if a hardware trigger is not
' detected before the 5 second timeout expires.
triggerDetected = app.Acquisition.Acquire(5, true)
```

Calibrate Action

Description

Initiates a full calibration of the acquisition system of the instrument.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Start a calibration.
app.Acquisition.Calibrate
```

CalibrateAll Action

CalNeeded Integer

Range From -2147483648 to 2147483647 step 1

Description

Query: Indicates whether calibration is required or not.

Based on hexadecimal bit value, it provides following information:

0x00000001: Front end calibration is required 0x00000002: Digitizers delay matching is required 0x00000004: Digitizers gain matching is required 0x00000008: Trigger level calibration is required 0xFFFFFFFF(-1): All of above calibrations are required

ClearSweeps Action

Description

Resets any accumulated average data or persistence data for channel waveforms (C1..C4). Valid only when one or more channels have waveform averaging or persistence enabled in their pre-processing settings. Note that an average may be reset on an individual basis using app.Acquisition.Cx.ClearSweeps control.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Clear accumulated sweeps for channels C1...C4
app.Acquisition.ClearSweeps
' Clear accumulated sweeps for only C1
app.Acquisition.C1.ClearSweeps
```

HorOffset Double

Range From -2.5e-007 to 2.5e-007 step 1e-009

Description

same as "app.Acquisition.Horizontal.HorOffset.cvar"

TriggerMode Enum

Description

Sets/Queries the trigger mode, using values from the following list - Auto, Norm, Normal, Single, Stopped.

Auto: After a timeout, if a real hardware trigger is not received, then force a trigger so there are automatically lots of updates.

Normal: Accepts triggers as rapidly as the system permits, but likewise will wait "forever" for a trigger, without updating anything.

Single: Arm the acquisition system to acquire once, and do not rearm automatically after. Once a trigger is received and the data processed, the instrument finishes in the "Stopped" state.

Stop: Finishes the current acquisition and does not re-arm.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Place the instrument in stopped mode and take one acquisition.
app.Acquisition.TriggerMode = "Stopped"
app.Acquisition.Acquire(5)
```

Values

Auto	Auto-trigger
Normal	Normal Trigger
Single	Single Trigger
Stopped	No trigger possible, Stopped

AUXOUTPUT

app.Acquisition.AuxOutput

Controls for the Auxilliary output BNC, which can be programmed as a simple square-wave signal source, or as a pulse which is asserted when various events occur, including Trigger Enabled, Trigger Out, and Pass/Fail.

Amplitude	Double
AuxInCoupling	Enum
AuxMode	Enum
CalMode	Enum
Frequency	DoubleLockstep
Mode	Enum

Example

```
' Microsoft Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

'Setup the Auxiliary output to be a squarewave with an amplitude of 500mV a frequency of 5kHz app.Acquisition.AuxOutput.Mode = "Square" app.Acquisition.AuxOutput.Amplitu

Amplitude Double

Range From 0.05 to 1 step 0.001

Description

Sets/Queries the amplitude of the signal on the AUX OUT connector. Note that this is the amplitude of the signal into a 1Mohm load. Into 50 ohms the output voltage will be halved (since the source impedance is nominally 50 ohms). Units are Volts.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the amplitude of the signal from the AUX OUT connector
' to 0.6 V into 1 megohm, or 0.3 V into 50 ohms.
app.Acquisition.AuxOutput.Amplitude = 0.6
```

AuxInCoupling Enum

Description

Sets the input coupling for the Auxiliary input path.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the coupling of the Auxiliary socket, when used as an input, to ground.
' In this condition, no input signal reaches the instrument.
app.Acquisition.AuxOutput.AuxInCoupling = "GND"
```

Values

DC50	DC, 50ohms coupling
GND	Grounded

AuxMode Enum

Description

Configures AUX Output type in WR and WS series of scopes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the Auxiliary output to trigger output signal.
app.Acquisition.AuxOutput.AuxMode = "TriggerOut"
```

Values

Off	No output
PassFail	Pulse on Pass fail condition
TriggerEnabled	Trigger enabled signal from trigger circuitry.
TriggerOut	Internal trigger output signal from trigger circuitry

CalMode Enum

Description

Configures Cal Output type in WR and WS series of scopes.

Example

```
' Follwoing example will set CAL output to 1 KHz, 0.5V square wave.
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set cal output to Square wave
app.Acquisition.AuxOutput.CalMode = "Square"
' Set cal output amplitude to 0.5 V with 1 MOhm impedence
app.Acquisition.AuxOutput.Amplitude = "0.5"
' Set cal output frequency to 1 KHz
app.Acquisition.AuxOutput.Frequency = "1000"
```

Values

DCLevel	DC Level with 1 Mohm o/p impedence
Off	Off
Square	Square wave

Frequency DoubleLockstep

Range From 250 to 1e+006 step 10, locked to 1 2.5 5, fine grain allowed=false, on=false

Description

This control only has effect when the AuxOutput mode is "Square".

Sets/Queries the auxiliary output frequency of the squarewave. Units are Hertz. Note that WaveMaster models (and derivatives) have a limit of 5MHz, WavePro 7000 models (and derivatives) have a limit of 1MHz.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the frequency of the signal from the AUX OUT
' connector to 1 MHz.
app.Acquisition.AuxOutput.Frequency = 1e6
```

Mode Enum

Description

Sets/Queries the output mode of the AUX OUT connector. (Applicable to WM, SDA, DDA, WP series of scopes)

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the output of the AUX OUT connector to output
' a pulse on a pre-determined Pass-Fail decision.
app.Acquisition.AuxOutput.Mode = "PassFail"
```

Values

DCLevel	Emit a DC level
Off	Output Disabled
PassFail	Pulse-out controlled by Pass/Fail system
Square	Square-wave signal generator
TriggerEnabled	Pulse-out when trigger is enabled
TriggerOut	Pulse-out when trigger occurs

CHANNELS

app.Acquisition.Channels

This group of variables controls the acquisition channels C1, C2, C3 and C4.

Names of the form app. Acquisition. Channels.xxxx are aliases of simpler names which are described in the section of the manual which is devoted to app. Acquisition. Examples of alias pairs are as follows -

```
app.Acquisition.Channels("Cx") is equivalent to app.Acquisition.Cx app.Acquisition.Channels(1) is equivalent to app.Acquisition.C1 app.Acquisition.Channels("Cx").Out.Result is equivalent to app.Acquisition.Cx.Out.Result
```

Example

```
Set app = CreateObject("LeCroy.XStreamDSO")
For X = 1 To 4
    app.Acquisition.Channels(X).VerScale = 0.2
Next
```

CX app.Acquisition.Cx

This group of variables controls the input channels C1, C2, C3 and C4.

Names of the form app.Acquisition.Channels.xxxx are aliases of simpler names which are described in the section of the manual which is devoted to app.Acquisition. Examples of alias pairs are as follows -

app.Acquisition.Channels("Cx") is equivalent to app.Acquisition.Cx app.Acquisition.Channels("Cx").Out.Result is equivalent to app.Acquisition.Cx.Out.Result

AverageSweeps	Integer
AxisXRotation	Integer
AxisYRotation	Integer
BandwidthLimit	Enum
ClearSweeps	Action

Coupling	Enum
Deskew	Double
EnhanceResType	Enum
FindScale	Action
InterpolateType	Enum
Invert	Bool
LabelsPosition	String
LabelsText	String
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ProbeAttenuation	Double
ProbeName	String
ShowLastTrace	Bool
UseGrid	String
VerOffset	Double
VerScale	DoubleLockstep
VerScaleVariable	Bool
View	Bool
ViewDecode	Bool
ViewLabels	Bool

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Setup Channel C1
app.Acquisition.C1.VerScale = 0.5
app.Acquisition.C1.VerOffset = 0.0
app.Acquisition.C1.Coupling = "DC50"
' Setup Channel C2
app.Acquisition.C2.VerScale = 0.1□
```

AverageSweeps Integer

Range From 1 to 1000000 step 1

Description

Sets/Queries the number of averaging sweeps for input channel Cx. This is distinct from the math function app.Math.Fx. If the number of sweeps is 1 (the default value), the data will not be averaged.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the number of sweeps for channel C1 to 25.
app.Acquisition.C1.AverageSweeps = 25
```

AxisXRotation Integer

Range From -90 to 90 step 1

Description

Sets/Queries the state of the X Axis rotation control, used only in 3-D persistence modes to control the viewing position. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the rotation about the X-axis to 35 degrees for trace C3.
app.Acquisition.C3.AxisXRotation = 35
```

AxisYRotation Integer

Range From -90 to 90 step 1

Description

Sets/Queries the state of the Y Axis rotation control, used only in 3-D persistence modes to control the viewing position. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the rotation about the Y-axis to 25 degrees for trace C3.
app.Acquisition.C3.AxisYRotation = 25
```

BandwidthLimit Enum

Description

Sets/Queries the bandwidth limit for input channel Cx, in Hz. Note that this control is an enum, and therefore requires a string value, and not a scalar value.

Note that bandwidth limit choices vary between DSO models.

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
'Set the bandwidth limit for C2 to 20 MHz.
app.Acquisition.C2.BandwidthLimit = "20MHz"
```

Values

200MHz	
20MHz	
Full	

ClearSweeps Action

Description

Clears all accumulated average data and persistence data for this channel. See app.Acquisition.ClearSweeps for a control that clears accumulated data for channels 1..4, or app.ClearSweeps for a control that clears accumulated data for all subsystems (including Math/Measure/Display, etc.)

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Reset channel C1
app.Acquisition.C1.ClearSweeps
' Reset channels C1..C4
app.Acquisition.ClearSweeps
```

Coupling Enum

Description

Sets/Queries the input coupling of input channel Cx.

Note that coupling choices vary between instrument models. WavePro 7000 instruments for example support AC1M and DC1M modes in addition to DC50 and GND choices.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Inspect the input coupling for channel C2
CoupleC2 = app.Acquisition.C2.Coupling
' Set the coupling to DC, 50 ohms
app.Acquisition.C2.Coupling = "DC50"
```

Values

AC1M	
DC1M	
DC50	
Gnd	

Deskew Double

Range From -4.5e-007 to 4.5e-007 step 1e-012

Description

Sets/Queries the deskew of input channel Cx to produce a required alignment with another trace.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

EnhanceResType Enum

Description

Enhance resolution setting (Noise Filter). Set to 'None' to turn off the filter.

Values

0.5bits	
1.5bits	
1bits	
2.5bits	
2bits	
3bits	
None	

FindScale Action

Description

Starts FindScale operation for this chanel. This operation will adjust channel's v/div and offset control such that the signal is visible on the screen with in +/- 3 div.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
'Find vertical scale of channel 1
app.Acquisition.C1.FindScale
```

InterpolateType Enum

Description

Sets/Queries the type of interpolation used for input channel Cx. Note that Sinx/x interpolation increases the size of the trace by a factor of 10, beware when using this option with long records.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the interpolation for channel C3 to (sin x)/x
app.Acquisition.C3.InterpolateType = "Sinxx"
```

Values

Linear	Linear interpolation
Sinxx	Sinx/x interpolation

Invert Book

Description

Sets/Queries whether input channel Cx is inverted.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set channel C2 to be inverted.
app.Acquisition.C2.Invert = True
```

Labels Position String

Range Any number of characters

Description

Sets / Queries the horizontal position of the label attached to the acquisition trace Cx. The unit of measurement is the unit of the horizontal scale. The measurement is made from the trigger point. Note that this control is a string, not a numeric value. This allows multiple labels to be positioned, as shown in the example below.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Add a couple of labels to trace C1, one at Ons, and one at 55ns app.SetToDefaultSetup app.Acquisition.C1.ViewLabels = True app.Acquisition.C1.LabelsPosition = "0.0,55e-9" app.Acquisition.C1.LabelsText = "Hello,World"
```

LabelsText String

Range Any number of characters

Persist3DQuality

Enum

Description

Sets/Queries the state of the 3D Persistence quality control, which controls the way that the persistence trace is rendered. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set persistence 3-D to shaded for trace C2.
app.Acquisition.C2.Persist3DQuality = "Shaded"
```

Values

Shaded	
Solid	
WireFrame	

Persisted Bool

Description

Sets/Queries the persisted state of the waveform. If the Display.LockPersistence control is set to 'AllLocked' then the persisted state of all displayed waveforms will be the same. If the Display.LockPersistence control is set to 'PerTrace' then the persisted state of each waveform may be independently controlled.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set persistence on for trace C1
app.Display.LockPersistence = "PerTrace"
app.Acquisition.C1.Persisted = True
```

Persistence3d Bool

Description

Sets/Queries the 3D persistence state. If True, then the persistence display for this channel will be displayed as a three dimensional surface map. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set persistence plot as 3-D for trace C1
app.Acquisition.C1.Persistence3D = True
```

PersistenceMonoChrome

Bool

Description

Sets/Queries the monochrome persistence state. If True, then the persistence display for this channel will be monochromatic, whether 2-D or 3-D. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set persistence monochrome on for trace C4.
app.Acquisition.C4.PersistenceMonoChrome = True
```

PersistenceSaturation

Integer

Range From 0 to 100 step 1

Description

Sets/Queries the saturation threshold for persisted waveforms.

All information at this level or above will be recorded with the same color or intensity.

See the general description above for a discussion of the locked and unlocked persistence modes.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the persistence saturation level for trace C1.
app.Acquisition.C1.PersistenceSaturation = 60
```

PersistenceTime Enum

Description

Sets/Queries the state of the Persistence Time control. Controls the persistence decay time for this trace. See the general description above for a discussion of the locked and unlocked persistence

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the persistence time for the persistence trace of channel C1 to 10
```

seconds.

app.Acquisition.C1.PersistenceTime = "10s"

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

Double **ProbeAttenuation**

From 1e-006 to 10000 step 1e-006 Range

Description

Sets/Queries the probe attenuation. The probe attenuation is the factor by which the signal is made smaller, for example, 10 means that the probe divides by 10, and is referred to as a ÷10 probe. Note that certain passive probes may be marked as 'x10', even though they actually divide the input signal by a factor of 10.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the probe attenuation for channel C1 to 100
app.Acquisition.Cl.ProbeAttenuation = 100
```

ProbeName String

Any number of characters Range

Description

Queries the name of connected probe.

ShowLastTrace Bool

Description

Sets/Queries the state of the Show Last Trace control. If True then when this trace is displayed in persistence mode the last acquired waveform will be superimposed on the accumulating persistence map.

See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Makes the last acquired trace invisible for the
' persistence trace of channel C1.
app.Acquisition.C1.ShowLastTrace = False
```

UseGrid String

Range Any number of characters

Description

Sets/Queries the graticule on which the trace is displayed. Typical values include:

YT1..YT8: one of the YT graticules used in Single, Dual, Quad, and Octal display modes.

NotOnGrid: not displayed on any graticule.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Switch to dual grid mode, place C1 on the lower graticule
' and C2 on the upper graticule.
app.Display.GridMode = "Dual"
app.Acquisition.C1.UseGrid = "YT2"
app.Acquisition.C2.UseGrid = "YT1"
```

VerOffset Double

Range From -1 to 1 step 0.0005

Description

Sets/Queries the vertical offset of input channel Cx. The setting resolution in volts lies in the range 0.25% to 0.5%, depending on the numerical value.

Note that the available offset range is dependent upon the current V/Div setting, and also the instrument model.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the vertical offset for C1 to 10 mV.
app.Acquisition.C1.VerOffset = 0.01
```

VerScale DoubleLockstep

Range From 0.002 to 10 step 0.0005, locked to 1 2 5, fine grain allowed=true, on=false

Description

Sets/Queries the vertical scale (in Volts/Division) of an input channel. When variable gain (VerScaleVariable control) is disabled, the control will clip values to a 1..2..5 sequence. When variable gain is enabled, the setting resolution lies in the range 1% to 2%, depending upon the numerical value.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set C1 to a scale of 250mV/Div in Variable Scale mode app.Acquisition.C1.VerScaleVariable = True app.Acquisition.C1.VerScale = 0.25
```

VerScaleVariable Book

Description

Sets/Queries the state of the variable vertical scale control for channel Cx. When the variable scale is enabled, the setting resolution lies in the range 1% to 2%, depending on the numerical value. If a knowledge of the exact value is important, the value should be read back after a setting has been made.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the variable vertical scale for C1 to On.
app.Acquisition.C1.VerScaleVariable = True
```

View Bool

Description

Sets/Queries the channel's 'Viewed' state. When True the channel waveform is displayed on one of the display graticules. Note that even when a channel is not visible it may be used as a source for Math, Measure, etc.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Make channel C3 visible.
app.Acquisition.C3.View = True
```

ViewDecode Book

ViewLabels Book

Description

Sets/Queries whether the user-defined labels for the trace are visible. See Also: LabelsPosition and LabelsText controls.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Show the user-defined label for trace C2.
app.Acquisition.C2.ViewLabels = True
```

RESULT

app.Acquisition.Cx.Out.Result

Properties of the type xxxx.Out.Result.yyyy are those of the last completed acquisition. They are not affected if other controls are changed after that acquisition was completed. This distinction between "Out.Result" properties and other controls is most important when the trigger mode is Single or Stopped. You should treat "Out.Result" properties as read-only.

Several of these properties mention the 'frame', this is the term used to describe the visible portion of the trace, which is generally smaller than the acquired waveform. The frame could be used for example to display a 500pt. window onto a 1Mpt. Trace, or vertically it could be used to show the 'center' 10mV of a 100mV pk trace.

For a full overview of the properties of waveform (or other) results, please see Chapter 1.

HORIZONTAL

app.Acquisition.Horizontal

This group of variables controls the timebase, the sampling, and the trigger delay.

AcquiredSegments	Integer
AcquisitionDuration	Double
ActiveChannels	Enum
ExtClockFrequency	Double
ExtCoupling	Enum
HorOffset	Double
HorOffsetOrigin	Double
HorScale	DoubleLockstep
HorUnits	String
MaxSamples	DoubleLockstep
NumPoints	Integer
NumSegments	Integer
ReferenceClock	Enum
SampleClock	Enum
SampleMode	Enum
SamplingRate	Double
SequenceTimeout	Double
SequenceTimeoutEnable	Bool
SetExtClockFrequency	Bool

SmartMemory	Enum
Source	Enum
TimePerPoint	Double
UseLegacyDefault	Enum

AcquiredSegments

Integer

Range From 0 to 100000 step 1

Acquisition Duration

Double

Range From 1e-012 to 1e+012 step 1e-015

Description

Queries the duration of the last completed acquisition. The result may depend on the spacing of the triggers in sequence mode, and it may depend on the number of averages when a channel is in averaging mode.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

'Obtain the duration of the last completed acquistion. AcqDuration = app.Acquisition.Horizontal.AcquisitionDuration MsgBox AcqDuration

ActiveChannels Enum

Description

Sets/Queries the number of active DSO input channels.

Note that this is a string value, the allowed values are "4", "2" and "Auto", and 0, 1, and 2. Beware of using 2 as a numerical value for 2 channels: you will get Auto mode instead.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Set the instrument to use two channels. app.Acquisition.Horizontal.ActiveChannels = "2"

Values

2	Use all channels
4	
Auto	Maximize sample rate based upon the # displayed channels

ExtClockFrequency

Double

Range From 0.001 to 100000 step 0.001

ExtCoupling Enum

Description

Specific to WR and WS series of the scope. Sets/Queries coupling of external trigger/clock input.

Values

DC1M	
DC50	

HorOffset Double

Range From -0.0005 to 2.5e-007 step 1e-009

Description

Sets/Queries the horizontal position of the trigger time, relative to the origin set by HorOffsetOrigin, in seconds. Positive to the right, negative to the left. The setting resolution is about 1% to 2&.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the horizontal trigger offset to 200 ns.
app.Acquisition.Horizontal.HorOffset = 2.0e-7
```

HorOffsetOrigin Double

Range From 0 to 10 step 1

Description

Sets/Queries the origin, in graticule divisions, of the time scale in which HorOffset is measured. The value 0 corresponds to the left edge of the graticule. The value 10 corresponds to the right edge of the graticule. Requesting a value outside the range will select the nearest allowed value.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the origin of the horizontal trigger offset to 4.0 divisions.
app.Acquisition.Horizontal.HorOffsetOrigin = 4.0
```

HorScale DoubleLockstep

Range From 2e-010 to 1000 step 5e-010, locked to 1 2 5, fine grain allowed=false, on=false

Description

Sets/Queries the horizontal scale in time per division.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the horizontal acquisition scale to 200 ns/div.
app.Acquisition.Horizontal.HorScale = 2.0e-7
```

HorUnits String

Range Any number of characters

Description

Queries the units in which the horizontal scale is measured.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Obtain the units of the horizontal scale.
HorizUnit = app.Acquisition.Horizontal.HorUnits
```

MaxSamples DoubleLockstep

Range From 500 to 5e+007 step 1000, locked to 1 2.5 5, fine grain allowed=false, on=false

Description

Sets/Queries the maximum permissible number of samples to be used in the acquisition memories. At the faster sample rates, the actual number used may be less than this maximum.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the available memory length per channel to 500
app.Acquisition.Horizontal.MaxSamples = 500
```

NumPoints Integer

Range From 2 to 100000000 step 1

Description

Queries the number of samples in the current setting of the acquisition memory. For sequence mode, this refers to the number if samples per segment, not to the number in the complete set.

Use MaxSamples to limit the number of samples acquired.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Obtain the number of points being used in the acquisition memory.
NumberOfPoints = app.Acquisition.Horizontal.NumPoints
MsgBox NumberOfPoints
```

NumSegments Integer

Range From 2 to 10000 step 1

Description

Sets/Queries the number of segments in the sequence mode of acquisition. Only valid when SampleMode = "Sequence'

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Enable sequence mode and capture 500 segments
app.Acquisition.Horizontal.SampleMode = "Sequence"
app.Acquisition.Horizontal.NumSegments = 500
```

ReferenceClock Enum

Description

Sets/Queries the source of the acquisition reference clock.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the source of the reference clock to External.
app.Acquisition.Horizontal.ReferenceClock = "EXT"
```

Values

EXT	External reference (use rear-panel BNC)
INT	Internal reference clock

SampleClock Enum

Description

Sets/Queries the source for the sample clock.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the sample clock to expect an external source.
app.Acquisition.Horizontal.SampleClock = "External"
```

Values

INT	

SampleMode Enum

Description

Sets/Queries the mode of acquisition as real-time or sequence or random interleaved sampling. Note that RIS mode and sequence mode are not available over the entire range of time-bases, and are not available simultaneously.

WaveExpert differences: CIS and SEQ are the only timebase modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the mode of acquisition to random interleaved sampling.
app.Acquisition.Horizontal.SampleMode = "RIS"
' WaveExpert example
app.Acquisition.Horizontal.SampleMode = "CIS"
```

Values

RealTime	
Sequence	
WStream	

SamplingRate Double

Range From 500 to 5e+009 step (2 digits)

Description

Queries the sampling rate. This is the effective sampling rate of the traces, rather than the sample rate of the ADCs.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Inspect the effective sampling rate of the signal.
SamplingRate = app.Acquisition.Horizontal.SamplingRate
```

SequenceTimeout Double

Range From 0.01 to 100 step 0.01

Description

Sets/Queries the timeout in segment mode of acquisition if insufficient triggers are received.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the sequence mode timeout to 10 seconds
app.Acquisition.Horizontal.SequenceTimeout = 10.0
```

SequenceTimeoutEnable

Bool

Description

Sets/Queries the enabling of the sequence mode timeout.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Enable the sequence mode timeout.
app.Acquisition.Horizontal.SequenceTimeoutEnable = True
```

SetExtClockFrequency

Bool

SmartMemory Enum

Description

Sets the mode of memory management to one of the two modes -

SetMaximumMemory - Maximizes the memory length for the given timebase setting, limited by the maximum length that is compatible with the maximum sample rate that the DSO can achieve. FixedSampleRate - Keeps the sample rate the same when the timebase is changed, limited by the maximum sample rate that the DSO can achieve.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the Smart memory mode as fixed sample rate.
app.Acquisition.Horizontal.SmartMemory = "FixedSampleRate"
```

Values

SetMaximumMemory	Keeps the sample rate the same when the timebase is changed
SetMaximumMemory	Keeps the sample rate the same when the timebase is changed

Source Enum

Values



TimePerPoint Double

From 1e-012 to 1e+012 step 1e-012 Range

Description

Queries the time interval between successive samples in the acquisition.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Obtain the time per point of the acquisition. timePerPt = app.Acquisition.Horizontal.TimePerPoint MsqBox timePerPt

UseLegacyDefault

Enum

Values

Never	
No	
Yes	

TRIGGER

app.Acquisition.Trigger

This group of cvars controls all aspects of the trigger, except for trigger delay, which is in Acquisition. Horizontal.

Names of the form app. Acquisition. Trigger. Sources.xxxx are aliases of simpler names which are described in this section of the manual. Examples of alias pairs are as follows -

app.Acquisition.Trigger.Sources("Cx") is equivalent to app.Acquisition.Trigger.Cx app.Acquisition.Trigger.Sources("Ext") is equivalent to app.Acquisition.Trigger.Ext app.Acquisition.Trigger.Sources("Line") is equivalent to app.Acquisition.Trigger.Line

Please see under Acquisition. Channels ("Cx") for a programming example.

HoldoffType	Enum
PatternType	Enum
ProbeName	String
Source	Enum
Туре	Enum
ZeroLevel	Action

HoldoffType Enum

Description

Sets/Queries type of hold-off trigger.

Values

Events	Holdoff by events, specified in HoldoffEvents
Off	No Trigger Holdoff
Time	Holdoff by time, specified in HoldoffTime

PatternType Enum

Description

Sets/Queries the pattern (Logic) trigger type.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the pattern trigger type to Nand.
app.Acquisition.Trigger.Type = "Logic"
app.Acquisition.Trigger.PatternType = "Nand"
```

Values

And	
Nand	
Nor	
Or	

ProbeName String

Range Any number of characters

Description

The name of the probe connected to the Ext trigger input ("None" if no probe is present)

Source Enum

Description

Sets/Queries the trigger source.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the trigger source to external.
```

app.Acquisition.Trigger.Source = "Ext"

Values

C1	
C2	
C3	
C4	
D0	
D1	
D10	
D11	
D12	
D13	
D14	
D15	
D16	
D17	
D18	
D19	
D2	
D20	
D21	
D22	
D23	
D24	
D25	
D26	
D27	
D28	
D29	
D3	
D30	
D31	
D32	
D33	
D34	
D35	
D4	

D5	
D6	
D7	
D8	
D9	
Ext	
ExtDivide10	
Line	

Type Enum

Description

Sets/Queries the trigger type (mode).

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the trigger type to glitch.
app.Acquisition.Trigger.Type = "Glitch"
```

Values

Dropout	
Edge	
Glitch	
Interval	
Logic	
Qualify	
Runt	
Serial	
SlewRate	
State	
TV	
Width	

ZeroLevel Action

Description

Sets the trigger level to zero volts.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the trigger level to zero volts.
app.Acquisition.Trigger.ZeroLevel
```

CX

app.Acquisition.Trigger.Cx

This group of variables controls triggering from the input channels C1, C2, C3 and C4.

InputImpedance	Enum
----------------	------

Level	Double
Level2	Double
PatternState	Enum
Slope	Enum
WindowSize	Double

InputImpedance Enum

Description

Reads the input impedance of channel C1, in Ohms

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Read the input impedance of C1 trigger.
ZinC1 = app.Acquisition.Trigger.C1.InputImpedance
```

Values

MsgBox ZinC1

50

Level Double

Range From -0.205 to 0.205 step 0.0005

Description

Sets/Queries the trigger level for the internal trigger from channel Cx. The setting resolution ranges from about 1.5% to about 2.5%, depending on the numerical value.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Set the trigger level to 55 mV for triggering on channel C1.
app.Acquisition.Trigger.C1.Level = 0.055
```

Level2 Double

Range From -0.205 to 0.205 step 0.0005

PatternState Enum

Description

Sets/Queries the pattern state for the input channel Cx. Only valid when the trigger mode is set to 'Logic'.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the pattern state for channel C1 to low.
app.Acquisition.Trigger.C1.PatternState = "Low"
```

Values

DontCare	
High	
Low	

Slope Enum

Description

Sets/Queries the direction of the transition to be used for internal triggering from channel Cx.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the direction of the transition as negative
' for triggering on channel C1.
app.Acquisition.Trigger.C1.Slope = "Negative"
```

Values

Either	
Negative	
Positive	
Window	

WindowSize Double

Range From 0.02 to 0.205 step 0.0005

DIGITAL

app.Acquisition.Trigger.Digital

Coupling	Enum
InputImpedance	Enum
Level	Double
Level2	Double
PatternState	Enum
Slope	Enum
WindowSize	Double

Coupling			Enum
Values			
InputImpe	edance		Enum
Values			
	50		
Level			Double
	From -1 to 1 step 0.0	001	2000.0
Range	110111-1 to 1 step 0.0	501	
Level2			Double
Range	From -1 to 1 step 0.0	001	
PatternSt			Enum
ratternot	ate		Liidiii
Values			
	DontCare		
	High		
	Low		
Slope			Enum
-			
Values			
	Either		
	Negative		
	Positive		
	Window		
WindowS	ize		Double
Range	From -1 to 1 step 0.0	001	
EXT		app.Acquisi	tion.Trigger.Ext
This group	of variables controls th	ne external trigger.	
	Coupling	Enum	
	InputImpedance	Enum	
	Level	Double	
	Level2	Double	
	PatternState	Enum	
	Slope	Enum	
	WindowSize	Double	

Enum

Coupling

Description

Sets/Reads the input coupling of the external trigger input.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Read the input coupling of the external trigger input. ZinCoupling = app.Acquisition.Trigger.Ext.Coupling MsgBox ZinCoupling

Values

AC	
DC	
HFREJ	
LFREJ	

InputImpedance Enum

Description

Reads the input impedance of the external trigger.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Read the input impedance of external trigger input. ZinExt = app.Acquisition.Trigger.Ext.InputImpedance MsgBox ZinExt

Values

50

Level Double

Range From -0.41 to 0.41 step 0.001

Description

Sets/Queries the trigger level for the external trigger.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the trigger level to 55 mV for triggering from
' the external trigger socket.
app.Acquisition.Trigger.Ext.Level = 0.055
```

Level2 Double

Range From -0.41 to 0.41 step 0.001

PatternState Enum

Description

Sets/Queries the pattern state for the external trigger input.

Example

- ' Visual Basic Script
 Set app = CreateObject("LeCroy.XStreamDSO")
- ' Set the pattern state to low for triggering from
- ' the external trigger socket.

app.Acquisition.Trigger.Ext.PatternState = "Low"

Values

DontCare	
High	
Low	

Slope Enum

Description

Sets/Queries the direction of the transition used for the external trigger.

Example

- ' Visual Basic Script
 Set app = CreateObject("LeCroy.XStreamDSO")
- ' Set the direction of the transition as positive for triggering
- ' from the external trigger socket.

app.Acquisition.Trigger.Ext.Slope = "Positive"

Values

Either	
Negative	
Positive	
Window	

WindowSize Double

Range From 0.04 to 0.41 step 0.001

SERIAL

app.Acquisition.Trigger.Serial

LevelAbsolute	Double
LevelHighAbsolute	Double
Protocol	Enum

LevelAbsolute Double

Range From 0 to 5 step 0.1

Description

Defines the threshold level applied to Serial data inputs (Data, Clock, CS)

LevelHighAbsolute

Double

Range From 0 to 5 step 0.1

Description

Defines the upper threshold level applied to tri-modal Serial Data protocol inputs (FlexRay)

Protocol Enum

Description

Defines the actual active trigger Serial standard (Protocol)

Values

CAN	
FLX	
I2C	
128	
LIN	
MIL1553	
RS232	
SPI	
UART	

I2C

app.Acquisition.Trigger.Serial.I2C

AckCondition	Enum
AddressLength	Enum
AddressValue	BitPattern
AddressWithRW	Bool
AtPosition	Enum
ByteBitOrder	Enum
DefaultLevel	Double
Direction	Enum
FrameCondition	Enum
NeedDualLevels	Bool
NeededSources	Enum
PatternLength	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
SupportsDigital	Bool
ViewingMode	Enum

AckCondition Enum

Values			
	Ack		
	DontCare		
	NoAck		
AddressL	ength		Enum
Values			
	10Bits		
	7Bits		
AddressV	alue		BitPattern
Range		nBits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X izeAlign=BitFix Format=Ehex	
AddressW	/ithRW		Bool
AtPositio	n		Enum
Values			
-	DontCare		
	Value		
ByteBitOr	der		Enum
Values			
	LSB		
	MSB		
DefaultLe	vel		Double
Range	From -1.79769e-	+308 to 1.79769e+308 step 0.001	
Direction			Enum
Values			
	DontCare		
	Read		
	Write		

ndition	Enum
Addr	
AddrData	
EEPROM	
FrameLength	
NoAck	
Restart	
Start	
Stop	
Levels	Bool
ources	Enum
ClockSource	
DataSource	
ngth	Integer
From 0 to 12 step 1	
perator	Enum
Equal	
Greater	
SmallerOrEqual	
lue	BitPattern
MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=PadAlign=Left SizeAlign=ByteVar Format=Ehex	=01X PaddingChar=X
lue2	BitPattern
MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=PadAlign=Left SizeAlign=ByteVar Format=Ehex	=01 PaddingChar=0
Digital	Вооі
	Addr AddrData EEPROM FrameLength NoAck Restart Start Stop Levels Durces ClockSource DataSource DataSource Tequal Greater GreaterOrEqual InRange NotEqual OutRange Smaller SmallerOrEqual Ilue MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=PadAlign=Left SizeAlign=ByteVar Format=Ehex Iue2 MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=PadAlign=Left SizeAlign=ByteVar Format=Ehex

ViewingMode Enum

Values

STD

Binary	
Hex	

CAN

app.Acquisition.Trigger.Serial.Protocol (Standard = "CAN")

AdaptedSamplingPoint	Double
AddressFormat	Enum
AddressOperator	Enum
AddressValue	BitPattern
AddressValue2	BitPattern
BitRate	Double
ByteOrder	Enum
DefaultLevel	Double
NeedDualLevels	Bool
NeededSources	Enum
NumSamplingPoints	Enum
PatternBitLength	Integer
PatternBitPos	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
RequestedSamplingPoint	Double
SignType	Enum
SupportsDigital	Bool
SymbolDBC	FileName
SymbolicOperator	Enum
SynchJumpWidth	Integer
TriggerCondition	Enum
Tseg1	Integer
Tseg2	Integer
ViewingMode	Enum

AdaptedSamplingPoint Range From 20 to 90 step 0.01 AddressFormat Values ALL EXT

AddressC	perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
AddressV	'alue		BitPattern
Range		s=11 NumBytes=2 AllowedBitValues=01X PaddingChar=X lign=BitFix Format=Ehex	
AddressV	alue2		BitPattern
Range		s=11 NumBytes=2 AllowedBitValues=01 PaddingChar=1 lign=BitFix Format=Ehex	
BitRate			Double
Range	From 10000 to 1e+0	006 step 1	
ByteOrde	r		Enum
Values			
	Intel		
	Motorola		
DefaultLe	vel		Double
Range		8 to 1.79769e+308 step 0.001	
NeedDua	Levels		Вооі
NeededS	ources		Enum
Values			
	DataSource		
NumSam	plingPoints		Enum
Values			
	1		

PatternBi	tLength		Integer
Range	From 0 to 64 step 1		
PatternBi	tPos		Integer
Range	From 0 to 63 step 1		
PatternO _l	perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
PatternVa	llue		BitPattern
Range	MaxBits=64 NumBits=8 NumBi	Bytes=1 AllowedBitValues=01X PaddingChar=λ x Format=Ehex	(
PatternVa	lue2		BitPattern
Range	MaxBits=64 NumBits=8 NumE PadAlign=Left SizeAlign=BitFi	Bytes=1 AllowedBitValues=01 PaddingChar=0 x Format=Ehex	
Requeste	dSamplingPoint		Double
Range	From 20 to 90 step 0.01		
SignType			Enum
Values			
	SignedInt		
	UnsignedInt		
Supports	Digital		Bool
SymbolD	BC		FileName
	Any number of characters		

Symbolic	Operator			Enum
Values				
	Equal			
	Greater			
	GreaterOrEqual			
	InRange			
	NotEqual			
	OutRange			
	Smaller			
	SmallerOrEqual			
SynchJur	mpWidth			Integer
Range	From 1 to 4 step 1			
TriggerCo	ondition			Enum
Values				
	All			
	Error			
	ID			
	IdData			
	Remote			
Tseg1				Integer
Range	From 3 to 16 step 1			
Tseg2				Integer
Range	From 2 to 8 step 1			
ViewingM	lode			Enum
Values				
	Binary			
	Hex			
	Sym			
FLX		app.Acquisition.Trigger.Se	rial.Protocol (Sta	nndard = "FLX")
	BitRate		Double	
	ByteBitOrder		Enum	
	CycleCountOperator		Enum	
	CycleCountValue		Integer	
	CycleCountValue2		Integer	
	DefaultLevel		Double	

FrameIDOperator	Enum
FrameIDValue	BitPattern
FrameIDValue2	BitPattern
NeedDualLevels	Bool
NeededSources	Enum
NullFrameInd	Enum
PatternLength	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
PayloadChannel	Enum
PayloadPreamble	Enum
RepetitionFactor	Enum
StartupFrameInd	Enum
SupportsDigital	Bool
SymbolCAS	Bool
SymbolCID	Bool
SymbolWakeup	Bool
SyncFrameInd	Enum
TriggerCondition	Enum
TrigOnBadBSS	Bool
TrigOnBadDTS	Bool
TrigOnBadFES	Bool
TrigOnBadFSS	Bool
TrigOnBadSymbol	Bool
TrigOnHeaderCRCError	Bool
TrigOnPayloadCRCError	Bool
ViewingMode	Enum

BitRate	Double

Range From 2.5e+006 to 1e+007 step 500000

ByteBitOrder Enum

Values

LSB	
MSB	

CycleCou	untOperator	Enum
Values		
	Equal	
	Greater	
	GreaterOrEqual	
	InRange	
	NotEqual	
	OutRange	
	Smaller	
	SmallerOrEqual	
CycleCou	ıntValue	Integer
Range	From 0 to 63 step 1	
CycleCou	ıntValue2	Integer
Range	From 0 to 63 step 1	
DefaultLe	evel	Double
Range	From -1.79769e+308 to 1.79769e+308 step 0.001	
FrameIDC	Operator	Enum
Values		
	Equal	
	Greater	
	GreaterOrEqual	
	InRange	
	NotEqual	
	OutRange	
	Smaller	
	SmallerOrEqual	
FrameIDV	/alue	BitPattern
Range	MaxBits=11 NumBits=11 NumBytes=2 AllowedBitValues=01X Pa PadAlign=Left SizeAlign=BitFix Format=Ehex	ddingChar=X
FrameIDV	/alue2	BitPattern
Range	MaxBits=11 NumBits=11 NumBytes=2 AllowedBitValues=01 Pade PadAlign=Left SizeAlign=BitFix Format=Ehex	dingChar=0
NeedDual	ILevels	Bool

Values DataSource	
DataSource	
DataGource	
NullFrameInd	Enum
Values	
One	
Zero	
PatternLength In	teger
Range From 0 to 12 step 1	
PatternOperator E	Enum
Values	
Equal	
Greater	
GreaterOrEqual	
InRange	
NotEqual	
OutRange	
Smaller	
SmallerOrEqual	
	attern
Range MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X PadAlign=Left SizeAlign=ByteVar Format=Ehex	
PatternValue2 BitPa	attern
Range MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=01 PaddingChar=0 PadAlign=Left SizeAlign=ByteVar Format=Ehex	
PayloadChannel	Enum
Values	
ChannelA	
ChannelB	
PayloadPreamble #	Enum
Values	
One	
Zero	

Repeti	tionFactor	Enum Control of the C	
Val	ues		
	1		
	16		
	2		
	32		
	4		
	64		
	8		
Startu	pFrameInd	Enum	
Val	ues		
	One		
	Zero		
Suppo	ortsDigital	Воог	
Symbo	DICAS	Воог	
Symbo	OICID	Bool	
Symbo	olWakeup	Bool	
SyncF	rameInd	Enum	
Val	ues		
	One		
	Zero		
Trigge	rCondition	Enum	
Val	ues		
	Errors		
	Frame		
	Symbol		
	TSS		
TrigOı	nBadBSS	Воог	
TrigOı	nBadDTS	Bool	
TrigOı	nBadFES	Bool	
TrigOı	nBadFSS	Bool	
TrigOı	nBadSymbol	Вооі	

TrigOnl	HeaderCRCError		Bool
TrigOnl	PayloadCRCError		Bool
/iewing	gMode	E	num
Valu	ues		
	Binary		
	Hex		
	AckCondition	Enum	
	AddressLength	Enum	
	AddressValue	BitPattern	
	AddressWithRW	Bool	
	AtPosition	Enum	
	ByteBitOrder	Enum	
	DefaultLevel	Double	
	Direction	Enum	
	FrameCondition	Enum	
	NeedDualLevels	Bool	
	NeededSources	Enum	
	PatternLength	Integer	
	PatternOperator	Enum	
	PatternValue	BitPattern	

AckCondition				
Values				
	Ack			
	NoAck			
AddressL	ength	Enum		
Values				
	10Bits			
	7Bits			

BitPattern

Bool

Enum

BitPattern

Range MaxBits=10 NumBits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X PadAlign=Left SizeAlign=BitFix Format=Ehex

PatternValue2

SupportsDigital

ViewingMode

AddressValue

AddressV	VithRW	Вооі
AtPositio	n	Enum
Values		
7 414.00	Value	
ByteBitO	rder	Enum
Values		
values		
	LSB MSB	
	MSB	
DefaultLe	evel	Double
Range	From -1.79769e+308 to 1.79769e+308 step 0.001	
Direction		Enum
Values		
	Read	
	Write	
FrameCo	ndition	Enum
Values		
	Addr	
	AddrData	
	EEPROM	
	FrameLength	
	NoAck	
	Restart	
	Start	
	Stop	
NeedDual	ILevels	Вооі
NeededSo	OUICAS	Enum
Necacao	our des	Enam
Values		
	ClockSource	
	DataSource	
PatternLe	ength	Integer
Range	From 0 to 12 step 1	

PatternOperator	Enum
-----------------	------

Values

Equal	
Greater	
GreaterOrEqual	
InRange	
NotEqual	
OutRange	
Smaller	
SmallerOrEqual	

PatternValue BitPattern

Range

MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X PadAlign=Left SizeAlign=ByteVar Format=Ehex

PatternValue2 BitPattern

Range

MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=01 PaddingChar=0 PadAlign=Left SizeAlign=ByteVar Format=Ehex

SupportsDigital Bool

ViewingMode Enum

Values

12S

Binary	
Hex	

app.Acquisition.Trigger.Serial.Protocol (Standard = "I2S")

AudioChannel	Enum
BitsInChannel	Integer
ByteBitOrder	Enum
ChipSelCondition	Enum
ClockPol	Enum
DefaultLevel	Double
EnableInterFrame	Bool
12SCondition	Enum
I2SVariant	Enum
NeedDualLevels	Bool
NeededSources	Enum
PatternBitsLen	Integer
PatternLength	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern

StartBitInChannel	Integer
SupportsDigital	Bool
TimeOutLenInNanoSec	Double
ViewingMode	Enum
WSFrameStart	Enum

AudioCha	annel	Enum
Values		
	Left	
	Right	
BitsInCha	annel	Integer
Range	From 1 to 32 step 1	
ByteBitO	rder	Enum
Values		
	LSB	
	MSB	
ChipSelC	condition	Enum
Values		
	Auto	
	Manual	
	None	
ClockPol		Enum
Values	;	
	Negative	
	Positive	
DefaultLe	evel	Double
Range	From -1.79769e+308 to 1.79769e+308 step 0.001	
EnableInt	terFrame	Bool

I2SCondi	tion	Enum
Values		
	Clip	
	Data	
	FallingEdge	
	Glitch	
	Mute	
	RisingEdge	
I2SVariar	nt	Enum
Values		
values	I2S	
	LJ	
	RJ	
	11.0	
NeedDua	lLevels	Bool
NeededS	ources	Enum
Values		
	ClockSource	
	CSSource	
	DataSource	
PatternBi	tsLen	Integer
Range	From 1 to 32 step 1	
PatternLe	ength	Integer
Range	From 0 to 8 step 1	
PatternO	perator	Enum
Values		
	Equal	
	Greater	
	GreaterOrEqual	
	InRange	
	NotEqual	
	OutRange	
	Smaller	
	SmallerOrEqual	

PatternVa	alue	BitPattern
Range	MaxBits=32 NumBits=32 NumBytes=4 AllowedBitValues=01X PaddingChar=X PadAlign=Right SizeAlign=BitVar Format=Ehex	
PatternVa	alue2	BitPattern
Range	MaxBits=32 NumBits=32 NumBytes=4 AllowedBitValues=01 PaddingChar=0 PadAlign=Right SizeAlign=BitVar Format=Ehex	
StartBitIn	Channel	Integer
Range	From 0 to 31 step 1	
Supports	Digital	Вооі
TimeOutL	-enInNanoSec	Double
Range	From 4e-008 to 0.0026214 step 4e-008	
ViewingN	lode	Enum
Values		
	Binary	
	Hex	
WSFrame	eStart	Enum
Values		
	Falling	
	Rising	

LIN

app.Acquisition.Trigger.Serial.Protocol (Standard = "LIN")

AddressOperator	Enum
AddressValue	BitPattern
AddressValue2	BitPattern
BitRate	Double
DefaultLevel	Double
NeedDualLevels	Bool
NeededSources	Enum
PatternLength	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
SupportsDigital	Bool
TriggerCondition	Enum
ViewingMode	Enum

AddressC	perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
Address	'alue		BitPattern
Range		6 NumBytes=1 AllowedBitValues=01X PaddingChar=X gn=BitFix Format=Ehex	
Address	alue2		BitPattern
Range		6 NumBytes=1 AllowedBitValues=01 PaddingChar=0 gn=BitFix Format=Ehex	
BitRate			Double
Range	From 300 to 20000 st	ep 1	
DefaultLe	vel		Double
Range	From -1.79769e+308	to 1.79769e+308 step 0.001	
NeedDua	Levels		Вооі
NeededS	ources		Enum
Values			
	DataSource		
PatternLe	enath		Integer
Range	From 0 to 8 step 1		3 ge.
•			

PatternO	perator		Enum
Values	3		
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
PatternVa	alue		BitPattern
		Dita O Numa Dita da A Allawad Dita /alwaa OAY Dadding Char Y	
Range		Bits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X zeAlign=ByteVar Format=Ehex	
PatternVa	alue2		BitPattern
Range		Bits=8 NumBytes=1 AllowedBitValues=01 PaddingChar=0 zeAlign=ByteVar Format=Ehex	
Supports	Digital		Bool
TriggerC	ondition		Enum
Values	S		
	Break		
	Error		
	FrameID		
	IDData		
ViewingN	l lode		Enum
Values	3		
	Binary		
	Hex		
MIL15	53	app.Acquisition.Trigger.Serial.Protocol (Standa	ard = "MIL1553"
	BitRate	Double	
	C1_ModeCode	Enum	
	C1_ModeCode(+	
	C1_RTAddress		

BitPattern

BitPattern BitPattern

Enum

Enum

C1_RTAddress2

C1_RTAddressOP

C1_RTSubAddress

C1_RTSubAddress2 C1_RTSubAddressOP

C1_WordCount	Integer
C1_XmitRcv	Enum
C2_ModeCode	Enum
C2_ModeCodeOP	Enum
C2_RTAddress	BitPattern
C2 RTAddress2	BitPattern
C2 RTAddressOP	Enum
C2_RTSubAddress	BitPattern
C2 RTSubAddress2	BitPattern
C2 RTSubAddressOP	Enum
C2 WordCount	Integer
C2 XmitRcv	Enum
D_PatternBitLength	Integer
D_PatternBitPos	Integer
D_PatternOperator	Enum
D PatternValue	BitPattern
D_PatternValue2	BitPattern
DefaultLevel	Double
IMGTimeFrom	Double
IMGTimeOperator	Enum
IMGTIMEOperation IMGTIMETO	Double
NeedDualLevels NeedDualLevels	Bool
NeededSources	Enum
RespTimeFrom	Double
RespTimeOperator	Enum
RespTimeTo	Double
RHSRatio	Integer
S1_BcastRcvdBit	Enum
S1_BusyBit	Enum
S1_DynBusCtrlBit	Enum
S1_InstrBit	Enum
S1_MsgErrorBit	Enum
S1_RTAddress	BitPattern
S1_RTAddress2	BitPattern
S1_RTAddressOP	Enum
S1_SRQBit	Enum
S1_SubSystFlagBit	Enum
S1_TermFlagBit	Enum
S2_BcastRcvdBit	Enum
S2_BusyBit	Enum
S2_DynBusCtrlBit	Enum
S2_InstrBit	Enum
S2_MsgErrorBit	Enum
S2_RTAddress	BitPattern
S2_RTAddress2	BitPattern
S2_RTAddressOP	Enum
<u> </u>	1

S2_SRQBit	Enum
S2_SubSystFlagBit	Enum
S2_TermFlagBit	Enum
SupportsDigital	Bool
TrigOnBadManchesterEncoding	Bool
TrigOnBadWordCount	Bool
TrigOnIdleError	Bool
TrigOnInvalidSync	Bool
TrigOnNonContiguousData	Bool
TrigOnParityError	Bool
TrigOnStatusAddressMismatch	Bool
TrigOnSyncError	Bool
Туре	Enum
TypeTransfer	Enum

BitRate Double

From 500000 to 4e+007 step 1000 Range

C1_ModeCode Enum

Values

0DynamicBusControl	
10Reserved	
11Reserved	
12Reserved	
13Reserved	
14Reserved	
15Reserved	
16TransmitVectorWord	
17Synchronize	
18TransmitLastComman	
19TransmitBITWord	
1Synchronize	
20SelectedTransmitterSh	
21OverrideSelectedTran	
22Reserved	
23Reserved	
24Reserved	
25Reserved	
26Reserved	
27Reserved	
28Reserved	
29Reserved	
2TransmitStatusWord	
30Reserved	
31Reserved	
3InitiateSelfTest	
4TransmitterShutdown	
5OverrideTransmitterShu	
6InhibitTerminalFlag	
7OverrideInhibitTerminal	
8ResetRemoteTerminal	
9Reserved	

C1_ModeCodeOP Enum

Values

Equal	
Greater	
GreaterOrEqual	
NotEqual	
Smaller	
SmallerOrEqual	

C1_RTAd	dress		BitPattern
Range		sits=5 NumBytes=1 AllowedBitValues=01X PaddingChar=X zeAlign=BitFix Format=Ehex	
C1_RTAd	dress2		BitPattern
Range		sits=5 NumBytes=1 AllowedBitValues=01 PaddingChar=0 zeAlign=BitFix Format=Ehex	
C1_RTAd	dressOP		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
1 DTC	bAddress		BitPattern
_			Diti attern
Range		tits=5 NumBytes=1 AllowedBitValues=01X PaddingChar=X zeAlign=BitFix Format=Ehex	
C1_RTSu	bAddress2		BitPattern
Range		sits=5 NumBytes=1 AllowedBitValues=01 PaddingChar=0 zeAlign=BitFix Format=Ehex	
C1_RTSu	bAddressOP		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
C1 Word	Count		Integer
	wiii		

Range From 0 to 31 step 1

C1_XmitRcv Enum

Values

0	
1	
X	

C2_ModeCode Enum

Values

0DynamicBusControl	
10Reserved	
11Reserved	
12Reserved	
13Reserved	
14Reserved	
15Reserved	
16TransmitVectorWord	
17Synchronize	
18TransmitLastComman	
19TransmitBITWord	
1Synchronize	
20SelectedTransmitterSh	
21OverrideSelectedTran	
22Reserved	
23Reserved	
24Reserved	
25Reserved	
26Reserved	
27Reserved	
28Reserved	
29Reserved	
2TransmitStatusWord	
30Reserved	
31Reserved	
3InitiateSelfTest	
4TransmitterShutdown	
5OverrideTransmitterShu	
6InhibitTerminalFlag	
70verrideInhibitTerminal	
8ResetRemoteTerminal	
9Reserved	

C2_Mode	CodeOP		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	NotEqual		
	Smaller		
	SmallerOrEqual		
C2_RTAd	dress		BitPattern
Range		5 NumBytes=1 AllowedBitValues=01X PaddingChar=X ign=BitFix Format=Ehex	
C2_RTAddress2			BitPattern
Range	MaxBits=5 NumBits=5 NumBytes=1 AllowedBitValues=01 PaddingChar=0 PadAlign=Left SizeAlign=BitFix Format=Ehex		
C2_RTAd	dressOP		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
C2_RTSu	bAddress		BitPattern
Range	MaxBits=5 NumBits=5 NumBytes=1 AllowedBitValues=01X PaddingChar=X PadAlign=Left SizeAlign=BitFix Format=Ehex		
C2_RTSu	bAddress2		BitPattern
Range	MaxBits=5 NumBits=5 NumBytes=1 AllowedBitValues=01 PaddingChar=0 PadAlign=Left SizeAlign=BitFix Format=Ehex		

C2_RTSu	bAddressOP	Enum
Values	:	
	Equal	
	Greater	
	GreaterOrEqual	
	InRange	
	NotEqual	
	OutRange	
	Smaller	
	SmallerOrEqual	
C2_WordCount		Integer
Range	From 0 to 31 step 1	
C2_XmitF	Rcv	Enum
Values	;	
	0	
	1	
	X	
D_Patteri	nBitLength	Integer
Range	From 0 to 16 step 1	
D_Patteri	nBitPos	Integer
Range	From 0 to 511 step 1	
D_Patteri	nOperator	Enum
Values		
	Equal	
	Greater	
	GreaterOrEqual	
	InRange	
	NotEqual	
	OutRange	
	Smaller	
	SmallerOrEqual	
D_Patteri	nValue	BitPattern
Range	MaxBits=16 NumBits=8 NumBytes=1 AllowedBitValues=01 PadAlign=Left SizeAlign=ByteVar Format=Ehex	X PaddingChar=X

D_Pattern	Value2		BitPattern
Range		=8 NumBytes=1 AllowedBitValues=01 PaddingChar=0 ign=ByteVar Format=Ehex	
DefaultLe	vel		Double
Range	From -1.79769e+308 to 1.79769e+308 step 0.001		
IMGTimeF	rom		Double
Range	From 0 to 3.2752e-005 step 8e-009		
IMGTimeC	Operator		Enum
Values			
	Greater		
	InRange		
	OutRange		
	Smaller		
IMGTimeT	o		Double
Range	From 0 to 3.2752e-00	05 step 8e-009	
NeedDual	Levels		Вооі
NeededSc	ources		Enum
Values			
	DataSource		
RespTime	From		Double
Range	From 0 to 3.2752e-00	05 step 8e-009	
RespTime	Operator		Enum
Values			
	Greater		
	InRange		
	OutRange		
	Smaller		
RespTime	То		Double
Range			
RHSRatio			Integer
Range	From 0 to 100 step 1		_

S1_E	BcastF	RcvdBit		Enum
٧	/alues			
		0		
		1		
		X		
S1_E	BusyB	it		Enum
V	/alues			
		0		
		1		
		Χ		
S1_[DynBu	sCtrlBit		Enum
V	/alues			
		0		
		1		
		Х		
S1_I	nstrBi	t		Enum
V	/alues			
		0		
		1		
		Χ		
S1_N	MsgEr	rorBit		Enum
V	/alues			
		0		
		1		
		Х		
S1_F	RTAdd	ress		BitPattern
Ra	ange		=5 NumBytes=1 AllowedBitValues=01X PaddingChar=X lign=BitFix Format=Ehex	
S1_F	RTAdd	ress2		BitPattern
Ra	ange	MaxBits=5 NumBits= PadAlign=Left SizeAl	-5 NumBytes=1 AllowedBitValues=01 PaddingChar=0 lign=BitFix Format=Ehex	

S1_R	RTAddressOP	Enum
Va	/alues	
	Equal	
	Greater	
	GreaterOrEqual	
	InRange	
	NotEqual	
	OutRange	
	Smaller	
	SmallerOrEqual	
S1_S	SRQBit	Enum
Va	/alues	
	0	
	1	
	Х	
S1_S	SubSystFlagBit	Enum
Va	/alues	
	0	
	1	
	Х	
S1_T	TermFlagBit	Enum
Va	/alues_	
	0	
	1	
	Х	
S2_B	BcastRcvdBit	Enum
Va	/alues	
	0	
	1	
	X	
S2_B	BusyBit	Enum
Va	/alues	
	0	
	1	
	Х	
	-	

S2_DynB	usCtrlBit		Enum
Values			
	0		
	1		
	Х		
S2_InstrE	Bit		Enum
Values			
	0		
	1		
	X		
S2_MsgE			Enum
Values	1		
	0		
	1		
	Х		
S2_RTAd	dress		BitPattern
Range		its=5 NumBytes=1 AllowedBitValues=01X PaddingChar=X eAlign=BitFix Format=Ehex	
S2_RTAd	dress2		BitPattern
Range	MaxBits=5 NumB PadAlign=Left Siz	its=5 NumBytes=1 AllowedBitValues=01 PaddingChar=0 eAlign=BitFix Format=Ehex	
S2_RTAd	dressOP		Enum
Values	:		
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
S2_SRQE	Bit		Enum
Values	;		
	0		
	1		
	Х		

S2_Sul	bSystFlagBit		Enum
Valu	ıes		
	0		
	1		
	X		
S2_Ter	mFlagBit		Enum
Valu	ıes		
	0		
	1		
	X		
Suppo	rtsDigital		Bool
TrigOn	BadManchesterEn	coding	Bool
TrigOn	BadWordCount		Bool
TrigOn	IdleError		Bool
TrigOn	InvalidSync		Bool
TrigOn	NonContiguousDa	ta	Bool
TrigOn	ParityError		Bool
TrigOn	StatusAddressMis	match	Bool
TrigOn	SyncError		Bool
Туре			Enum
Valu	ıes		
	Error		
	Timing		
	Transfer		
	Word		

TypeTransfer Enum

Values

All	
BCRTRcv	
Modecommand	
ModecommandDataRcv	
ModecommandDataXmit	
RTBCXmit	
RTRT	

RS232

app.Acquisition.Trigger.Serial.Protocol (Standard = "RS232")

AtPosition	Enum
BitRate	Double
ByteBitOrder	Enum
DefaultLevel	Double
FrameDelimiter	Enum
InterFrameMinBits	Integer
NeedDualLevels	Bool
NeededSources	Enum
NumDataBits	Integer
ParityType	Enum
PatternLength	Integer
PatternOperator	Enum
PatternPosition	Integer
PatternValue	BitPattern
PatternValue2	BitPattern
Polarity	Enum
RS232Mode	Bool
StopBitLength	Enum
SupportsDigital	Bool
TrigOnBadParity	Bool
UARTCondition	Enum
ViewingMode	Enum

AtPositio	on	Enum
Values	5	
	Value	
BitRate		Double
D	From 200 to 10,007 aton 1	

Range From 300 to 1e+007 step 1

ByteBitO	rder	Enum
Values		
	LSB	
DefaultLe	evel	Double
Range	From -1.79769e+308 to 1.79769e+308 step 0.001	
FrameDel	limiter	Enum
Values		
	Manual	
	None	
InterFram	neMinBits	Integer
Range	From 1 to 65535 step 1	
NeedDua	ILevels	Bool
NeededS	ources	Enum
Values		
	DataSource	
NumData	Bits	Integer
Range	From 5 to 8 step 1	
ParityTyp	e	Enum
Values		
	Even	
	None	
	Odd	
PatternLe	ength	Integer
Range	From 0 to 12 step 1	

PatternO	perator		Enum
Values	;		
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
PatternPo	osition		Integer
Range	From -1 to 2047 ste	ep 1	
PatternVa	alue		BitPattern
Range		ts=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X Align=ByteVar Format=Ehex	
PatternVa	alue2		BitPattern
Range		ts=8 NumBytes=1 AllowedBitValues=01 PaddingChar=0 Align=ByteVar Format=Ehex	
Polarity			Enum
Values	;		
	IdleLow		
RS232Mc	ode		Bool
StopBitL	ength		Enum
Values	;		
	1.5bit		
	1bit		
	2bits		
Supports	Digital		Bool
TrigOnBa	adParity		Bool
UARTCo	ndition		Enum
Values	;		
	Data		
		•	

ViewingMode	Enum
•	

Values

Binary	
Hex	

SPI

app.Acquisition.Trigger.Serial.Protocol (Standard = "SPI")

ByteBitOrder	Enum
ChipSelCondition	Enum
ClockPhase	Enum
ClockPolarity	Enum
CSPolarity	Enum
DefaultLevel	Double
EnableInterFrame	Bool
NeedDualLevels	Bool
NeededSources	Enum
PatternBitLength	Integer
PatternBitPos	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
SignType	Enum
SPIVariant	Enum
SupportsDigital	Bool
TimeOutLen	Double
ViewingMode	Enum

ByteBitOrder Enum

Values

LSB	
MSB	

ChipSelCondition Enum

Values

Auto	
Manual	

ClockPha	ase	Enum
Values	S	
	0	
	1	
ClockPol	larity	Enum
Values	S	
	0	
	1	
CSPolari	ty	Enum
Values	S	
	ActiveHigh	
	ActiveLow	
DefaultLe	evel	Double
Range	From -1.79769e+308 to 1.79769e+308 step 0.001	
EnableIn	terFrame	Bool
NeedDua	ılLevels	Вооі
NeededS	Sources	Enum
Values	S	
	ClockSource	
	CSSource	
	DataSource	
PatternB	itLength	Integer
Range	From 0 to 96 step 1	
PatternB	itPos	Integer
Range	From 0 to 95 step 1	

PatternOp	erator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
•	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
PatternVa	lue		BitPattern
Range		Bits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X eAlign=BitVar Format=Ehex	
PatternVa	lue2		BitPattern
Range		Bits=8 NumBytes=1 AllowedBitValues=01 PaddingChar=0 eAlign=BitVar Format=Ehex	
SignType			Enum
Values			
	SignedInt		
	UnsignedInt		
SPIVarian	t		Enum
Values			
values	DDD		
	DDR		
	SIOP		
	SSPI		
Supports	Digital		Bool
TimeOutL	en		Double
Range	From 4e-008 to 0.	0026214 step 4e-008	
ViewingM	ode		Enum
Values			
Ī	Binary		
	Hex		
UART		app.Acquisition.Trigger.Serial.Protocol (St	andard = "UART")

AtPosition	Enum
Bit9State	Enum
BitRate	Double
ByteBitOrder	Enum
DefaultLevel	Double
FrameDelimiter	Enum
InterFrameMinBits	Integer
NeedDualLevels	Bool
NeededSources	Enum
NumDataBits	Integer
ParityType	Enum
PatternLength	Integer
PatternOperator	Enum
PatternPosition	Integer
PatternValue	BitPattern
PatternValue2	BitPattern
Polarity	Enum
StopBitLength	Enum
SupportsDigital	Bool
TrigOnBadParity	Bool
UARTCondition	Enum
ViewingMode	Enum

AtPositio	n		Enum
Values			
	Value		
Bit9State			Enum
Values			
	0		
	1		
	X		
BitRate			Double
Range	From 300 to 1e+007	step 1	
ByteBitO	rder		Enum
Values			
	LSB		
	MSB		

DefaultLe	evel		Double
Range	From -1.79769e+308	3 to 1.79769e+308 step 0.001	
FrameDe	limiter		Enum
Values	3		
	Manual		
	None		
InterFran	neMinBits		Integer
		0.1	
Range	From 1 to 65535 step	p i	
NeedDua	lLevels		Bool
NeededS	ources		Enum
Values	5		
	DataSource		
NumData	Bits		Integer
Range	From 5 to 9 step 1		
ParityTyp	 D e		Enum
Values	5		
	Even		
	None		
	Odd		
PatternLe	ength		Integer
Range	From 0 to 12 step 1		
PatternO	perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
PatternPo	osition		Integer
Range	From -1 to 2047 step	0.1	

PatternVa	llue	BitPattern
Range	MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X PadAlign=Left SizeAlign=ByteVar Format=Ehex	
PatternVa	ilue2	BitPattern
Range	MaxBits=96 NumBits=8 NumBytes=1 AllowedBitValues=01 PaddingChar=0 PadAlign=Left SizeAlign=ByteVar Format=Ehex	
Polarity		Enum
Values		
	IdleHigh	
	IdleLow	
StopBitLe	ength	Enum
Values		
	1.5bit	
	1bit	
	2bits 2bits	
Supports	Digital	Bool
TrigOnBa	dParity	Bool
UARTCor	dition	Enum
Values		
	Data	
ViewingN	lode	Enum
Values		
	Binary	
	Hex	
		app.Cursors
CHRS	1K >	app.GuiS01S

CURSURS

This set of variables controls the cursor system.

Track	Bool
Туре	Enum
View	Bool
XPos1	Double
XPos2	Double
YPos1	Double
YPos2	Double

Track Bool

Description

Sets/Queries the state of tracking of a pair of cursors. If tracking is enabled then when the first cursor is moved, the second will track at a constant distance from it.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set cursors tracking on.
app.Cursors.Track = True
```

Type Enum

Description

Sets/Queries the currently selected type of cursor.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the cursor type to vertical relative.
app.Cursors.View = "On"
app.Cursors.Type = "VertRel"
```

Values

HorizAbs	Single cursor, position specified in time
HorizRel	Dual cursors, positions specified in time
VertAbs	Single cursor, position specified in divisions vertically
VertRel	Dual cursors, positions specified in divisions vertically

View Bool

Description

Sets/Queries visibility of the cursors.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Make the cursors visible.
app.Cursors.View = "On"
```

XPos1 Double

Range From -1.79769e+308 to 1.79769e+308 step 0

Description

Sets/Queries the horizontal position of the first cursor, in the units of the horizontal variable.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the horizontal position of the first cursor to 50 ns.
app.Cursors.XPos1 = 50e-9
```

XPos2 Double

Range From -1.79769e+308 to 1.79769e+308 step 0

Description

Sets/Queries the horizontal position of the second cursor, in the units of the horizontal variable.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the horizontal position of the second cursor to 4.5 ms.
app.Cursors.XPos2 = 4.5e-3
```

YPos1 Double

Range From -3.99 to 3.99 step 0.01

Description

Sets/Queries the vertical position of the first cursor, in graticule divisions.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the vertical position of the first cursor.
app.Cursors.YPos1 = 3.4
```

YPos2 Double

Range From -3.99 to 3.99 step 0.01

Description

Sets/Queries the vertical position of the second cursor, in graticule divisions.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the vertical position of the second cursor.
app.Cursors.YPos2 = 2.1
```

DISPLAY app.Display

This set of variables controls the properties of the screen display of the instrument.

AxisLabels	Bool
AxisXRotation	Integer
AxisYRotation	Integer
C1Color	Color
C1PrintColor	Color
C2Color	Color
C2PrintColor	Color
C3Color	Color
C3PrintColor	Color
C4Color	Color

C4PrintColor	Color
ClearSweeps	Action
DisplayMode	Enum
F1Color	Color
F1PrintColor	Color
F2Color	Color
F2PrintColor	Color
F3Color	Color
F3PrintColor	Color
F4Color	Color
F4PrintColor	Color
FactoryDefault	Action
GridIntensity	Integer
GridMode	Enum
GridOnTop	Bool
LockPersistence	Enum
M1Color	Color
M1PrintColor	Color
M2Color	Color
M2PrintColor	Color
M3Color	Color
M3PrintColor	Color
M4Color	Color
M4PrintColor	Color
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceLastTrace	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceStyle	Enum
PersistenceTime	Enum
PreviewPrintColors	Action
ResetAll	Action
SegmentMode	Enum
TraceIntensity	Double
TraceStyle	Enum

AxisLabels Book

Description

Sets/Queries the visibility of the labels that show the horizontal and vertical limits of each grid.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

```
' Show the axis labels.
app.Display.AxisLabels = True
```

AxisXRotation Integer

Range From -90 to 90 step 1

Description

Sets/Queries the rotation angle, about the X-axis, of the 3-D persistence display. The X-axis runs horizontally in the plane of the screen. Positive or negative angles may be used. Positive or negative angles may be used, in the range - 90 to + 90 degrees. Zero produces a direct plan, viewed perpendicularly. Zero produces a direct plan view, if Y rotation is also zero.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the rotation about the X axis to 45 degrees.
app.Display.AxisXRotation = 45
```

AxisYRotation Integer

Range From -90 to 90 step 1

Description

Sets/Queries the rotation angle, about the Y-axis, of the 3-D persistence display. The Y-axis runs vertically in the plane of the screen. Positive or negative angles may be used, in the range - 90 to + 90 degrees.

A positive angle makes the left side look closer than the right side. Zero produces a direct plan view, if X rotation is also zero.

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Set the rotation about the Y axis to 35 degrees.
app.Display.AxisYRotation = 35
```

C1Color Color

Range From 0 to 16777215

Description

Sets/Queries the color of trace C1, using a number in the range 0 to FFFFFF in hexadecimal. The possible colors are made from any combination of the primary colors, which are set in hexadecimal as Blue = &HFF0000, Green = &HFF00, Red = &HFF. The value may be entered in decimal or in hexadecimal, though hexadecimal is usually more convenient. Note that if the intensity of a color is to be reduced or increased by a numerical factor, an AND operation must be used afterwards, to prevent corruption of other primary colors.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

Red = &Hff: Green = &H80: Blue = &H00

' Set the color of channel C1 trace to orange
app.Display.C1Color = (Blue * &H10000) + (Green * &H100) + Red
```

Color C1PrintColor From 0 to 16777215 Range Description Sets/Queries the color, in the printing palette, of trace C1, using a number in the range 0 to FFFFFF in hexadecimal. The primary colors are Blue = &HFF0000, Green = &HFF00, Red = &HFF in The value may be entered in decimal or in hexadecimal. **Example** ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO") Red = &Hff: Green = &H80: Blue = &H00 ' Set the color of channel C1 trace to orange for printing. app.Display.C1PrintColor = (Blue * &H10000) + (Green * &H100) + Red C2Color Color From 0 to 16777215 Range Description Please see C1Color. C2PrintColor Color From 0 to 16777215 Range Description Please see C1Printcolor. C3Color Color From 0 to 16777215 Range Description Please see C1Color. C3PrintColor Color From 0 to 16777215 Range Description Please see C1Printcolor. C4Color Color From 0 to 16777215 Range Description Please see C1Color.

C4PrintColor Color

Range From 0 to 16777215

Description

Please see C1Printcolor.

ClearSweeps Action

Description

Initiates the Clear Sweeps operation. Clears history only for persistence traces, see the main Clear Sweeps control 'app.ClearSweeps', or the ClearSweeps control in other subsystems for other options.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Initiate a clear sweeps action for persistence traces.
app.Display.ClearSweeps
```

DisplayMode Enum

Description

Sets/Queries the display mode as either "Scope", showing the normal instrument screen, or "WebEdit", showing the web processor editing panel. Note that WebEdit mode is available only with certain software options, including XMATH and XMAP.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Switch to WebEdit mode
app.Display.DisplayMode = "WebEdit"
```

Values

Scope	
WebEdit	

F1Color Color

Range From 0 to 16777215

Description

Please see C1Color.

F1PrintColor Color

Range From 0 to 16777215

Description

Please see C1Printcolor.

F2Color Color

Range From 0 to 16777215

Description

Please see C1Color.

F2PrintColor Color From 0 to 16777215 Range Description Please see C1Printcolor. F3Color Color From 0 to 16777215 Range Description Please see C1Color. F3PrintColor Color From 0 to 16777215 Range Description Please see C1Printcolor. F4Color Color From 0 to 16777215 Range Description Please see C1Color. F4PrintColor Color Range From 0 to 16777215 Description Please see C1Printcolor. **FactoryDefault** Action Description Restores the display of the instrument to the factory default settings **Example** ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO")

' Restore the display to the factory pre-set state.

app.Display.FactoryDefault

GridIntensity Integer

Range From 0 to 100 step 1

Description

Sets/Queries the grid intensity as a percentage of the maximum value, with a resolution of 1%.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the grid intensity to 60% of the maximum.
app.Display.GridIntensity = 60
```

GridMode Enum

Description

Sets/Queries the grid mode. The commands "Single" and "Dual", for example, set the grid mode until countermanded. "Auto" allows the instrument to set the grid mode most suitable for the current number of visible traces.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Enter Octal grid mode
app.Display.GridMode = "Octal"
```

Values

Auto	Automatically choose grid mode, one trace per grid
Dual	Dual grid mode
Octal	Octal grid mode
Quad	Quad grid mode
Single	Single grid mode
XY	XY grid mode
XYDual	XY + Dual grid mode
XYSingle	XY + Single grid mode

GridOnTop Bool

Description

Sets/Queries whether the grid lines lie over the traces or vice versa.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the grid lines to be over the trace lines.
app.Display.GridOnTop = True
```

Enum

LockPersistence

Description Sets/Queries whether the persistence states of the visible traces are locked together or separate. **Example** ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO") ' Set the persistence display to per trace, not locked. app.Display.LockPersistence = "PerTrace" **Values** AllLocked PerTrace M1Color Color From 0 to 16777215 Range Description Please see C1Color. Color M1PrintColor Range From 0 to 16777215 Description Please see C1Printcolor. Color M2Color From 0 to 16777215 Range Description Please see C1Color. M2PrintColor Color From 0 to 16777215 Range Description Please see C1Printcolor. M3Color Color From 0 to 16777215 Range Description Please see C1Color. M3PrintColor Color From 0 to 16777215 Range Description Please see C1Printcolor.

M4Color Color

Range From 0 to 16777215

Description

Please see C1Color.

M4PrintColor Color

Range From 0 to 16777215

Description

Please see C1Printcolor.

Persist3DQuality Enum

Description

Sets/Queries the type of 3D plot that is displayed

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the type of the 3-D persistence plot.
app.Display.Persist3DQuality = "WireFrame"
```

Values

Shaded	
Solid	
WireFrame	

Persisted Book

Description

Sets/Queries whether persistence mode is in use. If the previously set persistence mode is per trace, the persisted cvar will be set as true by this command, even if none of the traces has been set to persistence mode.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Read the state of persistence mode.
Persist = app.Display.Persisted
```

Persistence3d Bool

Description

Sets/Queries whether the persistence 3-D mode is activated.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the 3-D display to off.
app.Display.Persistence3d = False
```

PersistenceLastTrace Bool

Description

Sets/Queries whether the last created trace is shown over the persistence trace.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the persistence display to show the last trace
' on top of the persistence trace.
app.Display.PersistenceLastTrace = True
```

PersistenceMonoChrome

Bool

Description

Sets/Queries whether the persistence mode is monochrome.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the persistence mode as color.
app.Display.PersistenceMonoChrome = False
```

PersistenceSaturation

Integer

Range From 0 to 100 step 1

Description

Sets/Queries the population level, relative to the maximum possible level, at which the persistence traces reach maximum intensity, and above which there are no further changes in color or intensity.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the persistence saturation level to 60%.
app.Display.PersistenceSaturation = 60
```

PersistenceStyle Enum

Description

Sets/Queries the type of persistence trace displayed.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the persistence style to color graded.
app.Display.PersistenceStyle = "ColorGraded"
```

Values

3d	
Analog	
ColorGraded	

PersistenceTime Enum

Description

Sets/Queries decay time for trace persistence, expressed as a number of seconds, or as "infinity".

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the persistence time to 10 seconds.
app.Display.PersistenceTime = "10s"
```

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

PreviewPrintColors Action

Description

Show the instrument display in the current color scheme selected for printing.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Show the current color scheme selected for printing.
app.Display.PreviewPrintColors
```

ResetAll Action

Description

Turns off persistence on any traces where it has been set on.

Example

app.Display.ResetAll

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Reset all persistence traces to non-persisted mode.
```

SegmentMode Enum

Description

Sets/Queries the display mode for segmented input channels. All visible channels are set to the same display mode by a single command.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the display mode for segments in C2 to perspective.
```

app.Acquisition.C2.SegmentMode = "Perspective"

Values

Adjacent	All segments displayed end-to-end, left to right
Mosaic	Segments displayed in a mosaic, top-left to bottom right
Overlay	Segments are overlaid, similar to persistence
Perspective	Segments are displayed in a perspecfive view
Waterfall	Successive segments are displayed with increasing vertical offset

TraceIntensity Double

Range From 1 to 100 step 1

Description

Control the intensity of traces.

TraceStyle Enum

Description

Sets/Queries the style in which traces are drawn.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Read the state of the persistence mode.
TraceStyle = app.Display.TraceStyle
```

Values

Line	Connect adjacent samples with straight lines
Points	Show only the sample points

ELECTRICALTELECOM

app.ElectricalTelecom

Root Automation node to control Electrical Telecom (ET-PMT) package. This package is performing Pulse Mask Test on different SONET/SDH standards.

ClearSweeps	Action
Polarity	Enum
Run	Action
Setup	Action
Source	Enum

Standard	Enum
Stop	Action
StopAfter	Integer
StopTesting	Bool
VerticalAlign	Action

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")

'Select an stadard, run the test and get results after a while app.ElectricalTelecom.Standard = "E1Tp"
app.ElectricalTelecom.Source = "C2"
app.ElectricalTelecom.Setup
app.ElectricalTelecom.Run
app.Sleep 10000
app.ElectricalTelecom.Pause
passed = CStr(app.ElectricalTelecom.NumPass)
tested = CStr(app.ElectricalTelecom.NumTested)
MsgBox passed + " passed of " + tested + " tests"
```

ClearSweeps Action

Description

The ClearSweeps allows you to reset the sweep count and start testing over again.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")

'Select an stadard, run the test and clear the counter after a while app.ElectricalTelecom.Standard = "ElCoax" app.ElectricalTelecom.Setup app.ElectricalTelecom.Run app.Sleep 5000 app.ElectricalTelecom.Pause app.Sleep 5000 app.ElectricalTelecom.ClearSweeps
```

Polarity Enum

Description

In many electrical standards, such as DS-1, alternate "ones" are inverted. Each time a one is transmitted it is either a positive or negative going pulse depending upon the polarity of the previous one. This type of coding is referred to as AMI (alternate mark inversion). The Polarity control allows you to select which polarity (positive or negative) pulse to test.

The STS-3E and STM-1E standards use CMI (code mark inversion) pulse coding. In CMI coding, a one remains high for the full bit period while a zero has a transition to the low state in the middle of the bit period. The Polarity control allows you to select whether a 1 or 0 is to be tested.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")

'Select a stadard and set polarity to 'neg'
app.ElectricalTelecom.Standard = "E1Coax"
app.ElectricalTelecom.Polarity = "neg"
app.ElectricalTelecom.Setup
```

Values

neg	Negative pulse
pos	Positive pulse

Run Action

Description

The Setup button applies the appropriate settings to the oscilloscope for testing the selected standard. Different standards require a particular termination, and an error message will appear at the bottom of the oscilloscope screen if the wrong (or no) adapter is present. However, this error will not prevent the instrument from making the measurement; that is, measurements can be made without the specific adapters. But if the signal is out of range for the standard, the setup operation will generate an error message and the Run button will be grayed out. The signal will appear on the screen, but no testing will be possible.

Before the Setup button is pressed, the Run and Clear Sweeps buttons appear grayed out. These buttons become available (not grayed out) upon successful completion of a setup. At that time, a Re-Align button will replace the Setup button.

```
'Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")

'Select an stadard and run the test
app.ElectricalTelecom.Standard = "E1Coax"
app.ElectricalTelecom.Setup
app.ElectricalTelecom.Run
app.Sleep 5000
app.ElectricalTelecom.Pause 'pause the test after 5 seconds
app.Sleep 5000
app.ElectricalTelecom.Run 'and continue after 5 other seconds
```

Setup Action

Description

After the Telecom Standard has been choosed, the Source set, the 'Setup' command will perform all acquisition setup, make the appropriate alignments and make test ready to run.

This is one of the action to control the state machine of Mask Testing: Setup, ReAlign, Stop, Pause, Run and VerticalAlign.

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")

'Select an stadard and run the test
app.ElectricalTelecom.Standard = "E1Coax"
app.ElectricalTelecom.Setup
app.ElectricalTelecom.Run
app.Sleep 5000
app.ElectricalTelecom.Pause 'pause the test after 5 seconds
```

Source Enum

Description

Specify on which channel (C1 to C4) the electrical signal to be tested is connected.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")

'Select an stadard and the source
app.ElectricalTelecom.Standard = "E1Coax"
app.ElectricalTelecom.Source = "C4"
app.ElectricalTelecom.Setup
```

Values

C1	
C2	
C3	
C4	

Standard Enum

Description

Select the Telecom Standards that will be used to make alignments and mask test. Available standards are listed in the 'Standard' field of this database:

D:\Masks\PulseMasksProp.mdb. (whithout spaces and special characters).

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")

'Select an stadard and the source
app.ElectricalTelecom.Standard = "E1Coax"
app.ElectricalTelecom.Source = "C4"
app.ElectricalTelecom.Setup
```

Values

ANSI T1 DS1 standard on 100 ohm line (using AP100)
ANSI T1 DS3 standard on 75 ohm coax (using PP090 probe)
ITU-T E1 on 75 ohm coax (using PP090 probe)
ITU-T E1 on 120 ohm twisted pairs (using AP120 probe)
ITU-T E2 on 75 ohm coax (using PP090 probe)
ITU-T E3 on 75 ohm coax (using PP090 probe)
ITU-T E4 on 75 ohm coax (using PP090 probe)
ITU-T STM-1E on 75 ohm coax (using PP090 probe)
ANSI T1 STS-1 on 75 ohm coax (using PP090 probe)
ANSI T1 STS-3E on 75 ohm coax (using PP090 probe)

Stop Action

Description

Stop the test and reset counters. After this command, a new 'Setup' must be made. This is one of the action to control the state machine of Mask Testing: Setup, ReAlign, Stop, Pause, Run and VerticalAlign.

```
'Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")

'Select an stadard and run the test
app.ElectricalTelecom.Standard = "ElCoax"
app.ElectricalTelecom.Setup
app.ElectricalTelecom.Run
app.Sleep 5000
app.ElectricalTelecom.Pause 'pause the test after 5 seconds
app.Sleep 5000
app.ElectricalTelecom.Stop 'Stop the test
```

StopAfter Integer

Range From 1 to 1000000000 step 1

Description

If app.ElectricalTelecom.StopTesting is "On", this specify the number of sweeps that will be done before test will be stopped. After that, counters could be read.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")
'Select an stadard, run the test and stop after 1000 sweeps
app.ElectricalTelecom.Standard = "ElCoax"
app.ElectricalTelecom.Source = "C2"
app.ElectricalTelecom.Polarity = "pos"
app.ElectricalTelecom.StopAfter = 1000
app.ElectricalTelecom.StopTesting = "On"
app.ElectricalTelecom.Setup
app.ElectricalTelecom.Run
do while app.ElectricalTelecom.TestState <> "Pause"
 app.Sleep 500
loop
passed = CStr(app.ElectricalTelecom.NumPass)
tested = CStr(app.ElectricalTelecom.NumTested)
MsgBox passed + " passed of " + tested + " tests"
```

StopTesting Book

Description

If this mode is "On", the test will stop after 'app.ElectricalTelecom.StopAfter' sweeps.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.WaveMasterApplication.1")
'Select an stadard, run the test and stop after 1000 sweeps
app.ElectricalTelecom.Standard = "E1Coax"
app.ElectricalTelecom.Source = "C2"
app. Electrical Telecom. Polarity = "pos"
app.ElectricalTelecom.StopAfter = 1000
app.ElectricalTelecom.StopTesting = "On"
app.ElectricalTelecom.Setup
app.ElectricalTelecom.Run
do while app.ElectricalTelecom.TestState <> "Pause"
  app.Sleep 500
loop
passed = CStr(app.ElectricalTelecom.NumPass)
tested = CStr(app.ElectricalTelecom.NumTested)
MsgBox passed + " passed of " + tested + " tests"
```

Vertical Align Action

Description

For test that allow that, it's possible to perform a Vertical re-alignment.

ET

app.ElectricalTelecom.ET

Aligned waveform output of Electrical Telecom package. From there, all it's diplay settings can be changed. See "executive setup" chapter for more details.

AxisXRotation	Integer
AxisYRotation	Integer
BipolarLevel	Double
ClearSweeps	Action
LabelsPosition	String
LabelsText	String
LFCutoff	Double
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ShowLastTrace	Bool
Source	Enum
UseGrid	String
View	Bool
ViewLabels	Bool

AxisXRotation Integer

Range From -90 to 90 step 1

AxisYRotation Integer

Range From -90 to 90 step 1

Description

This control is used only when Persisted is true and Persistence3d is true. It controls rotation about the Y axis of the view being persisted.

BipolarLevel Double

Range From -100 to 100 step 1e-005

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

Labels Position String

Range Any number of characters

Description

Sets / Queries the horizontal position of the label attached to the acquisition trace Cx. The unit of measurement is the unit of the horizontal scale. The measurement is made from the trigger point. Note that this control is a string, not a numeric value. This allows multiple labels to be positioned, as shown in the example below.

Range Any number of characters

LFCutoff
Range From 1 to 5e+010 step 4

Persist3DQuality Enum

Description

This control only has an effect when Persisted is true and Persistence3D is true. It controls whether the 3D view is shown as a wire frame (which can be monochrome or color graded), a solid (also can be monochrome or color graded), or a shaded solid (always monochrome). For WireFrame or Solid, if monochrome the brightness increases with height; if color graded the color changes from puple to red with height. "Shaded" present the solid as if it were lit from the upper left.

Values

Shaded	
Solid	
WireFrame	

Persisted Book

Description

Sets/Queries the persisted state of the waveform. If the Display.LockPersistence control is set to 'AllLocked' then the persisted state of all displayed waveforms will be the same. If the Display.LockPersistence control is set to 'PerTrace' then the persisted state of each waveform may be independently controlled.

Persistence3d Bool

Description

Changes the persistence map from a two-dimensional surface with brightness or color indicating the third dimension, to a perspective rendering of a three dimensional object, where the third dimension is shown as height above the surface formed by points which are not lit. In 3d, that surface is same color or brightness as points with one or very few hits so that the surface is visible; but that means points with one or very few hits cannot be distinguished from the background. See also Persist3DQuality, which controls the appearance of the 3D object.

PersistenceMonoChrome

Bool

Description

When this control is false (the default state), persistence is color graded. When this control is set to true, persistence is monochrome, in the color of the trace, and increasing number of hits is shown as increasing brightness. This control only has an effect when Persisted is true.

PersistenceSaturation

Integer

Range From 0 to 100 step 1

Description

Sets/Queries the saturation threshold for persisted waveforms.

All information at this level or above will be recorded with the same color or intensity.

See the general description above for a discussion of the locked and unlocked persistence modes.

	Automation Cor	mmand and Query Reference Manual - Control Reference	
Persisten	ceTime		Enum
Descrip	tion		
	e. See the general de	the Persistence Time control. Controls the persistence decay time for this scription above for a discussion of the locked and unlocked persistence	
Values			
	0.5s		
	10s		
	1s		
	20s		
	2s		
	5s		
	Infinite		
ShowLas	tTrace		Bool
Descrip			
map		acquired waveform will be superimposed on the accumulating persistence on above for a discussion of the locked and unlocked persistence modes.	Enum
Values			
	C1		
	C2		
	C3		
	C4		
JseGrid			String
Range	Any number of char	acters	ou mg
√iew			Bool
	/Queries the trace's 'V	/iewed' state. When true, the trace is displayed on one of the display when a trace is not visible, it may be used as a source for Math, Measure,	
√iewLabe	els		Bool
Descrip	tion		

Sets/Queries whether the user-defined labels for the trace are visible.

See Also: LabelsPosition and LabelsText controls.

RESULT

app.ElectricalTelecom.ET.Out.Result

HARDCOPY app.HardCopy

This set of variables controls the transfer of information about the screen display to destinations such as such as disc files, internal memories, printers and remote computers.

Destination	Enum
EMailMessage	String
GridAreaOnly	Bool
HardcopyArea	Enum
Orientation	Enum
PreferredFilename	String
Print	Action
PrintLogo	Bool
SelectedPrinter	Enum
StripChart	Bool
StripChartFactor	Enum
UseColor	Enum

Destination Enum

Description

Sets/Queries the destination for hard copy.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the destination for hard copy to e-mail.
app.Hardcopy.Destination = "EMail"
```

Values

Clipboard	Send to clipboard for pasting into other applications
EMail	Send image in an E-Mail
File	Store image in a file
Printer	Print to a local, or networked printer
Remote	Special case used for remote printing, not usually used

EMailMessage String

Range Any number of characters

Description

Sets/Queries the e-mail message.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Create the e-mail message - "Results for run 89".
app.Hardcopy.EMailMessage = "Results for run 89".
```

GridAreaOnly Bool

Description

Sets/Queries whether hard copy is of grid area only.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Read the status of Grid Area Only.
GridArea = app.Hardcopy.GridAreaOnly
```

HardcopyArea Enum

Description

Sets/Queries the area of the screen to be included in a hard copy.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Select the DSO screen area for hard copy.
app.HardCopyArea = "DSOWindow"
```

Values

DSOWindow	Include only the DSO window
FullScreen	Include the full display screen
GridAreaOnly	Include the grid area only (doesn't include menus)

Orientation Enum

Description

Sets/Queries the orientation for hard copy to landscape.

Valid only when emitting to a printer as opposed to a file, the clipboard, or an E-Mail.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the orientation for hardcopy to landscape.
app.Hardcopy.Orientation = "Landscape"
```

Values

Landscape	
Portrait	

PreferredFilename String

Range Any number of characters

Description

Sets/Queries the preferred file name to use for hard copy.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the preferred filename to PrintFile.
app.Hardcopy.PreferredFilename = "PrintFile"
```

Print Action

Description

Initiates a hard copy.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Initiate a hard copy.
app.Hardcopy.Print
```

PrintLogo Bool

Description

Control whether the LeCroy logo will be superimposed on hardcopies.

SelectedPrinter Enum

Description

Sets/Queries the selection of the printer for hard copy. Note that whitespace and punctuation are removed from the string.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Select BarbondaleTintJet as the printer for hardcopy
app.Hardcopy.SelectedPrinter = "BarbondaleTintJet"
```

Values

StripChart Bool

Description

Sets/Queries the status of strip chart mode of printing. Valid only when emitting to the internal printer.

StripChartFactor Enum

Description

Sets/Queries the scale factor for strip chart printing. Valid only when emitting to the internal printer.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the strip chart scale to 5 cm/division.
app.Hardcopy.StripChartFactor = "5cmdiv"
```

Values

100cmdiv	
10cmdiv	
1cmdiv	
200cmdiv	
20cmdiv	
2cmdiv	
50cmdiv	
5cmdiv	

UseColor Enum

Description

Defines the color scheme to be used when printing.

Values

BW	Optimized for black and white printers
Print	Use print colors (white background)
Std	As presented on DSO display

LABNOTEBOOK

app.LabNotebook

Provides access to the 'LabNotebook' feature. This allows the entire scope state (Waveforms, Setups, Display Images) to be stored, annotated, recalled, emailed, etc.

AttachFilesToEMail	Bool
BackupDatabase	Action
BackupFilename	String
BackupFolder	FileName
BackupToFolder	Action
BackupToMemoryStick	Action
ClearFilter	Action
CompactDatabase	Action
ConnectToFPHardCopy	Bool
CreateReport	Action
DeleteAll	Action
DeleteRecord	Action
EMailRecord	Action

FilterRecords	Action
FlashBackToRecord	Action
Format	Enum
HardcopyArea	Enum
InternalView	Action
MyLabNotebookMD	FileName
NextRecord	Action
PreviousRecord	Action
PrintRecord	Action
PromptBeforeSaving	Bool
RecordList	Enum
ReportLogo	FileName
ReportsDirectory	FileName
Save	Action
ScribbleBeforeSaving	Bool
StartNew	Action
UseDefaultLogo	Bool
UseDefaultTemplate	Bool
UsePrintColor	Bool
ViewRecord	Action
XSLTemplate	FileName

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

```
' Save the current state of the DSO into the Notebook app.LabNotebook.ScribbleBeforeSaving = False app.LabNotebook.PromptBeforeSaving = False app.LabNotebook.Save
```

```
' Create a PDF report, and store it in the root of drive
C:app.LabNotebook.ReportsDirectory = "C:\"
app.LabNotebook.Format = "PDF"
app.LabNotebook.CreateReport
```

```
'Send the report in an email app.Preferences.Email.Mode = "SMTP" app.Preferences.Email.DefaultRecipient = "somebody@somewhere.com" app.LabNotebook.EMailRecord
```

AttachFilesToEMail Bool

Description

If true, the DSO Setup, and all enabled waveforms will be attached to any emailed report.

BackupDatabase Action

Description

Backup the current LabNotebook database. Note that this control will present a modal dialog, prompting for the backup filename and folder.

Use the BackupToFolder control to skip the dialog.

BackupFilename String Any number of characters Range Description Contains the filename into which the LabNotebook is stored, when the BackupDatabase request is made. **BackupFolder FileName** Any number of characters Range Description Contains the folder into which the LabNotebook is stored, when the BackupDatabase request is made. **BackupToFolder** Action Description Create a backup of the current LabNotebook database into the file specified by the BackupFolder/BackupFilename controls. **BackupToMemoryStick** Action Description Create a backup of the current LabNotebook database into a file on an attached memory stick. ClearFilter Action Description Clear the NoteBook entry filter. Action CompactDatabase Description Compact the LabNotebook database. Useful if entries have been deleted from the database, to reclaim disk space. Bool ConnectToFPHardCopy Description If True, the front-panel 'Print Screen' button is overridden to create a LabNotebook entry instead of its normal function. CreateReport Action Description Create a report (PDF/RTF/HTML) of the currently selected notebook entry. **DeleteAll** Action Description Delete all LabNotebook entries. Note that this action will popup a modal dialog, requesting confirmation.

DeleteRecord Action

Description

Delete the currently selected LabNotebook record.

Note that this will popup a modal dialog requesting confirmation.

EMailRecord Action

Description

Email the currently selected record, in the selected format (PDF/RTF/HTML), to the recipient specified in the email setup (app.Preferences.Email).

FilterRecords Action

Description

Popup a dialog proposing various filtering methods, including date, and/or keword based filters.

FlashBackToRecord Action

Description

Restore (FlashBack) the scope to the state that it was in when the current lab notebook entry was saved.

This may include the setup, and active waveforms.

Format Enum

Description

File Format in which exported reports are saved.

Values

HTML	
PDF	Adobe Acrobat file
RTF	Rich-text file (MS Wordpad, Word, etc.)

HardcopyArea Enum

Description

Defines the region of the display that is stored when creating a new entry in the notebook.

Values

DSOWindow	Contents of DSO window, incl. dialog + menu bar
FullScreen	Entire windows display area
GridAreaOnly	Grid area only

InternalView Action

Description

View the selected Lab Notebook entry within the DSO's graticule area.

Contrast with the 'ViewRecord' control, which presents the selected Lab Notebook entry in an external HTML browser.

FileName MyLabNotebookMD Any number of characters Range Description Filename of the currently active Lab Notebook database. **NextRecord** Action Description Move to (select) the next entry in the notebook. **PreviousRecord** Action Description Move to (select) the previous entry in the notebook. **PrintRecord** Action Description Print the selected Lab Notebook entry. This action will present a popup allowing the target printer to be selected. **PromptBeforeSaving** Bool Description If true, the DSO will prompt the interactive user for a summary, and description, before the notebook entry is created. RecordList **Enum** Description The list of entries in the Lab Notebook, named using a GUID. **Values FileName** ReportLogo Any number of characters Range Description Contains the full pathname of the logo which will appear on Lab Notebook pages. **FileName** ReportsDirectory Any number of characters Range Description The directory in which Lab Notebook reports are created.

Description

Save

Initiate the creation of a new Lab Notebook entry.

Action

ScribbleBeforeSaving

Bool

Description

If True, the DSO will allow the interactive user to 'scribble' (annotate) the report page before it is saved.

StartNew

Action

Description

Start a new Lab Notebook. This action will prompt the interactive user for the filename of the new Lab Notebook database file.

UseDefaultLogo

Bool

Description

If True, the default logo is used on Lab Notebook pages. If False, the logo specifeid by the ReportLogo control is used instead.

UseDefaultTemplate

Bool

Description

If True, the default xsl template is used when creating reports from LabNotebook pages.

If False, the template file specified by the XSLTemplate control is used instead.

UsePrintColor

Bool

Description

If True, 'print colors' are used when storing an image of the display. These use a white background, as opposed to black, to save toner/ink.

ViewRecord Action

Description

View the selected Lab Notebook entry in an external HTML browser.

Contrast with the 'ViewInternal' control, which presents the selected Lab Notebook entry within the DSO's graticule area.

XSLTemplate FileName

Range Any number of characters

Description

Filename of the XSL template used in creating reports from Lab Notebook pages.

LOGICANALYZER

app.LogicAnalyzer

CombinedChannels	Enum
LevelC1	Double
LevelC2	Double
LevelC3	Double
LevelC4	Double
LevelExt	Double
LineNames	String
MSxxHysteresis0	Double
MSxxHysteresis1	Double

MSxxHysteresis2	Double
MSxxHysteresis3	Double
MSxxLogicFamily0	Enum
MSxxLogicFamily1	Enum
MSxxLogicFamily2	Enum
MSxxLogicFamily3	Enum
MSxxThreshold0	Double
MSxxThreshold1	Double
MSxxThreshold2	Double
MSxxThreshold3	Double

CombinedChannels Enum

Description

Select MS-500 operation mode. In "2Combine", sampling rate is up to 2 GS/s and you can use up to 18 digital input lines. In "NoCombine", sampling rate is up to 1 GS/s and you can use up to 36 digital input lines.

Values

2Combine	
NoCombine	

LevelC1 Double

Range From -0.205 to 0.205 step 0.0005

Description

The threshold level determines how the input signal is interpreted. Input voltages less than the threshold are converted to '0'. Input voltages greater than the threshold are converted to '1'. In this case, input is analog Channel 1.

LevelC2 Double

Range From -0.205 to 0.205 step 0.0005

LevelC3 Double

Range From -0.205 to 0.205 step 0.0005

LevelC4 Double

Range From -0.205 to 0.205 step 0.0005

LevelExt Double

Range From -0.41 to 0.41 step 0.001

LineNames String

Range Any number of characters

Description

List of Digital Line Names

MSxxHysteresis0	Double
Range From 0.5 to 0.5 step 0.02	
Description The minimum high voltage level is user definable by the hyste threshold. The maximu low voltage level is user definable by the threshold. The minimum hysteresis is 100 mV.	
MSxxHysteresis1	Double
Range From 0.5 to 0.5 step 0.02	
MSxxHysteresis2	Double
Range From 0.5 to 0.5 step 0.02	
MSxxHysteresis3	Double
Range From 0.5 to 0.5 step 0.02	
MSxxLogicFamily0 Description You can select various Logic Families, or select User Defined Values	and define a custom threshold crossing.
CMOS2.5V	
CMOS3.3V	
CMOS5V	
ECL	
LVDS	
PECL5V	
TTL	
UserDefined	
MSxxLogicFamily1 Values	Enum
CMOS2.5V	
CMOS3.3V	
CMOS5V	

CMOS2.5V	
CMOS3.3V	
CMOS5V	
ECL	
LVDS	
PECL5V	
TTL	
UserDefined	

MSxxLogicFamily2 Enum

Values

CMOS2.5V	
CMOS3.3V	
CMOS5V	
ECL	
LVDS	
PECL5V	
TTL	
UserDefined	

MSxxLogicFamily3

Enum

Values

CMOS2.5V	
CMOS3.3V	
CMOS5V	
ECL	
LVDS	
PECL5V	
TTL	
UserDefined	

MSxxThreshold0 Double

Range From 1.5 to 1.5 step 0.02

Description

If you select User Defined Logic Family, then you will be able to define the voltage level of threshold. The threshold level determines how the input signal is interpreted. Input voltages less than the threshold are converted to '0'. Input voltages greater than the threshold are converted to '1'.

MSxxThreshold1 Double

Range From 1.5 to 1.5 step 0.02

MSxxThreshold2 Double

Range From 1.5 to 1.5 step 0.02

MSxxThreshold3 Double

Range From 1.5 to 1.5 step 0.02

DIGITALX

app.LogicAnalyzer.Digitalx

BusName	String
Digital0	Bool
Digital1	Bool

Digital2	Bool
Digital3	Bool
Digital4	Bool
Digital5	Bool
Digital6	Bool
Digital7	Bool
Digital8	Bool
DisplayMode	Enum
LineHeight	Double
LineNames	String
UseGrid	String
VerPosition	Double
View	Bool

BusName	•	String
Range	Any number of characters	
Digital0		Вооі
Digital1		Вооі
Digital2		Вооі
Digital3		Вооі
Digital4		Вооі
Digital5		Вооі
Digital6		Вооі
Digital7		Вооі
Digital8		Вооі
DisplayMode		Enum
Values		
	Collapse	
	Expand	
LineHeight		Double
Range	From 0.2 to 10 step 0.02	
LineName	es	String
Range	Any number of characters	

UseGrid
Range Any number of characters

VerPosition
Range From -3.8 to 10 step 0.05

View

Roof

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.LogicAnalyzer.Digitalx.Out.Result

TRIGGER

app.LogicAnalyzer.Trigger

Digital Dattaur Agrand agric 0	E
DigitalPatternArrayLogic0	Enum
DigitalPatternArrayLogic1	Enum
DigitalPatternArrayLogic10	Enum
DigitalPatternArrayLogic11	Enum
DigitalPatternArrayLogic12	Enum
DigitalPatternArrayLogic13	Enum
DigitalPatternArrayLogic14	Enum
DigitalPatternArrayLogic15	Enum
DigitalPatternArrayLogic16	Enum
DigitalPatternArrayLogic17	Enum
DigitalPatternArrayLogic18	Enum
DigitalPatternArrayLogic19	Enum
DigitalPatternArrayLogic2	Enum
DigitalPatternArrayLogic20	Enum
DigitalPatternArrayLogic21	Enum
DigitalPatternArrayLogic22	Enum
DigitalPatternArrayLogic23	Enum
DigitalPatternArrayLogic24	Enum
DigitalPatternArrayLogic25	Enum
DigitalPatternArrayLogic26	Enum
DigitalPatternArrayLogic27	Enum
DigitalPatternArrayLogic28	Enum
DigitalPatternArrayLogic29	Enum
DigitalPatternArrayLogic3	Enum
DigitalPatternArrayLogic30	Enum
DigitalPatternArrayLogic31	Enum
DigitalPatternArrayLogic32	Enum

DigitalPatternArrayLogic33	Enum
DigitalPatternArrayLogic34	Enum
DigitalPatternArrayLogic35	Enum
DigitalPatternArrayLogic4	Enum
DigitalPatternArrayLogic5	Enum
DigitalPatternArrayLogic6	Enum
DigitalPatternArrayLogic7	Enum
DigitalPatternArrayLogic8	Enum
DigitalPatternArrayLogic9	Enum
MSxxDigitalTriggerSet	Enum
MSxxDigitalTriggerType	Enum
PatternType	Enum
StateBottomArrayC1	Enum
StateBottomArrayC2	Enum
StateBottomArrayC3	Enum
StateBottomArrayC4	Enum
StateBottomArrayExt	Enum

DigitalPatter	nArray	Logic0
---------------	--------	--------

Enum

Description

Allows to select a value for digital line 0 of Logic Pattern Trigger. Value can be Zero, One, Don't Care, Rising Edge, Falling Edge or Either Edge.

Values

DontCare	
EitherEdge	
FallingEdge	
One	
RisingEdge	
Zero	

DigitalPatternArrayLogic1

Enum

DontCare	
EitherEdge	
FallingEdge	
One	
RisingEdge	
Zero	

Digita	IPatternArrayLogic10	Enum
Va	lues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
Digita	IPatternArrayLogic11	Enum
Va	lues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	One RisingEdge	
Digita	RisingEdge Zero	Enum
	RisingEdge	Enum
	RisingEdge Zero IPatternArrayLogic12	Enum
	RisingEdge Zero IPatternArrayLogic12 lues	Enum
	RisingEdge Zero IPatternArrayLogic12 lues DontCare	Enum
	RisingEdge Zero IPatternArrayLogic12 Iues DontCare EitherEdge	Enum
	RisingEdge Zero IPatternArrayLogic12 lues DontCare EitherEdge FallingEdge	Enum
	RisingEdge Zero IPatternArrayLogic12 Iues DontCare EitherEdge FallingEdge One	Enum
Va	RisingEdge Zero IPatternArrayLogic12 Iues DontCare EitherEdge FallingEdge One RisingEdge	Enum
Va Digita	RisingEdge Zero IPatternArrayLogic12 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero	
Va Digita	RisingEdge Zero IPatternArrayLogic12 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic13	
Va Digita	RisingEdge Zero IPatternArrayLogic12 lues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic13 lues	
Va Digita	RisingEdge Zero IPatternArrayLogic12 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic13 Iues DontCare	
Va Digita	RisingEdge Zero IPatternArrayLogic12 lues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic13 lues DontCare EitherEdge	
Va Digita	RisingEdge Zero IPatternArrayLogic12 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic13 Iues DontCare EitherEdge FallingEdge FallingEdge	

_	PatternArrayLogic14	1	Enum
Valu	ues		
	DontCare		
	EitherEdge		
	FallingEdge		
	One		
	RisingEdge		
	Zero		
Digital Valu	PatternArrayLogic15		Enum
	DontCare		
	EitherEdge		
	FallingEdge		
	One		
	She		
	RisingEdge		
Digital	RisingEdge Zero		Enum
Digital Valu	RisingEdge Zero PatternArrayLogic16		Enum
	RisingEdge Zero PatternArrayLogic16		5num
	RisingEdge Zero PatternArrayLogic16 ues		5num
	RisingEdge Zero PatternArrayLogic16 ues DontCare		Enum
	RisingEdge Zero PatternArrayLogic16 Les DontCare EitherEdge		Enum
	RisingEdge Zero PatternArrayLogic16 Jes DontCare EitherEdge FallingEdge		Enum
	RisingEdge Zero PatternArrayLogic16 Les DontCare EitherEdge FallingEdge One		Enum
Valu	RisingEdge Zero PatternArrayLogic16 Les DontCare EitherEdge FallingEdge One RisingEdge		Enum Enum
Valu	RisingEdge Zero PatternArrayLogic16 Les DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic17		
Valu Digital	RisingEdge Zero PatternArrayLogic16 Les DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic17		
Valu Digital	RisingEdge Zero PatternArrayLogic16 Lies DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic17 Lies		
Valu Digital	RisingEdge Zero PatternArrayLogic16 Les DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic17 Les DontCare		
Valu Digital	RisingEdge Zero PatternArrayLogic16 Jes DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic17 Jes DontCare EitherEdge FallingEdge One ArrayLogic17 Jes DontCare EitherEdge FallingEdge One One		
Valu Digital	RisingEdge Zero PatternArrayLogic16 Jes DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic17 Jes DontCare EitherEdge FallingEdge FallingEdge FallingEdge		

Digita	alPatternArrayLogic18	Enum
Va	alues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
Digita	alPatternArrayLogic19	Enum
Va	alues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
	alPatternArrayLogic2 alues	Enum
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
Digita	alPatternArrayLogic20	Enum
Va	alues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
	·	

	PatternArrayLogic21	Enum
Val	ues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
Digita	PatternArrayLogic22	Enum
Val	ues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	One RisingEdge	
Digita		Enum
	RisingEdge Zero PatternArrayLogic23 ues	Enum
	RisingEdge Zero PatternArrayLogic23 ues DontCare	Enum
	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge	Enum
	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge	Enum
	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One	Enum
	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One RisingEdge	Enum
Val	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One RisingEdge Zero	Enum
Val	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One RisingEdge	Enum
Val Digita	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One RisingEdge Zero	
Val Digita	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic24	
Val Digita	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic24 ues	
Val Digita	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic24 ues DontCare	
Val Digita	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic24 ues DontCare EitherEdge	
Val Digita	RisingEdge Zero PatternArrayLogic23 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic24 ues DontCare EitherEdge FallingEdge FallingEdge FallingEdge	

	PatternArrayLogic25	Enum
Val	ues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
Digital Val	PatternArrayLogic26	Enum
vai	DontCare	
	EitherEdge	
	FallingEdge	
	One	
Digital	RisingEdge Zero PatternArrayLogic27	Enum
Digital Val	RisingEdge Zero PatternArrayLogic27	Enum
	RisingEdge Zero PatternArrayLogic27	Enum
	RisingEdge Zero PatternArrayLogic27 ues	Enum
	RisingEdge Zero PatternArrayLogic27 ues DontCare	Enum
	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge	Enum
	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge FallingEdge	Enum
	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge FallingEdge One	Enum
Val	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge FallingEdge One RisingEdge	Enum
Val Digital	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic28 ues	
Val Digital	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic28	
Val Digital	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic28 ues DontCare EitherEdge	
Val Digital	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic28 ues DontCare EitherEdge FallingEdge Zero	
Val Digital	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic28 ues DontCare EitherEdge FallingEdge One Cone RisingEdge Zero	
Val Digital	RisingEdge Zero PatternArrayLogic27 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic28 ues DontCare EitherEdge FallingEdge Zero	

5	PatternArrayLogic29	Enum
Val	ues	
	DontCare]
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
Digital	PatternArrayLogic3	Enum
Val	ues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	One RisingEdge	
Digital	RisingEdge Zero	
	RisingEdge	Enum
	RisingEdge Zero PatternArrayLogic30	Enum
	RisingEdge Zero IPatternArrayLogic30 ues	Enum
	RisingEdge Zero PatternArrayLogic30 ues DontCare	Enum
	RisingEdge Zero IPatternArrayLogic30 ues DontCare EitherEdge	Enum
	RisingEdge Zero IPatternArrayLogic30 ues DontCare EitherEdge FallingEdge	Enum
	RisingEdge Zero IPatternArrayLogic30 ues DontCare EitherEdge FallingEdge One	Enum
Val	RisingEdge Zero IPatternArrayLogic30 ues DontCare EitherEdge FallingEdge One RisingEdge	Enum
Val	RisingEdge Zero IPatternArrayLogic30 ues DontCare EitherEdge FallingEdge One RisingEdge Zero	
Val	RisingEdge Zero PatternArrayLogic30 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic31	
Val	RisingEdge Zero IPatternArrayLogic30 ues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic31 ues	
Val	RisingEdge Zero IPatternArrayLogic30 ues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic31 ues DontCare	
Val	RisingEdge Zero IPatternArrayLogic30 ues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic31 ues DontCare EitherEdge	
Val	RisingEdge Zero IPatternArrayLogic30 ues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic31 ues DontCare EitherEdge FallingEdge Zero	

Digital	PatternArrayLogic32	Enum
Val	ues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
Digital Val	PatternArrayLogic33 ues	Enum
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	One RisingEdge	
Digital	RisingEdge Zero	Foum
Digital Val	RisingEdge Zero PatternArrayLogic34	Enum
	RisingEdge Zero PatternArrayLogic34	Enum
	RisingEdge Zero PatternArrayLogic34 ues	Enum
	RisingEdge Zero PatternArrayLogic34 ues DontCare	Enum
	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge	Enum
	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge FallingEdge	Enum
	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge FallingEdge One	Enum
Val	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge FallingEdge One RisingEdge	Enum
Val	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic35	
Val Digital	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic35	
Val Digital	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic35 ues	
Val Digital	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic35 ues DontCare	
Val Digital	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic35 ues DontCare EitherEdge	
Val Digital	RisingEdge Zero PatternArrayLogic34 ues DontCare EitherEdge FallingEdge One RisingEdge Zero PatternArrayLogic35 ues DontCare EitherEdge FallingEdge FallingEdge FallingEdge FallingEdge	

Digita	IPatternArrayLogic4	Enum
Va	lues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	RisingEdge	
	Zero	
Digita	IPatternArrayLogic5	Enum
Val	lues	
	DontCare	
	EitherEdge	
	FallingEdge	
	One	
	One RisingEdge	
Digita	RisingEdge Zero	Enum
	RisingEdge	Enum
	RisingEdge Zero IPatternArrayLogic6	Enum
	RisingEdge Zero IPatternArrayLogic6 lues	Enum
	RisingEdge Zero IPatternArrayLogic6 lues DontCare	Enum
	RisingEdge Zero IPatternArrayLogic6 Iues DontCare EitherEdge	Enum
	RisingEdge Zero IPatternArrayLogic6 Iues DontCare EitherEdge FallingEdge	Enum
	RisingEdge Zero IPatternArrayLogic6 lues DontCare EitherEdge FallingEdge One	Enum
Val	RisingEdge Zero IPatternArrayLogic6 Iues DontCare EitherEdge FallingEdge One RisingEdge	Enum
Val	RisingEdge Zero IPatternArrayLogic6 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero	
Val	RisingEdge Zero IPatternArrayLogic6 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic7	
Val	RisingEdge Zero IPatternArrayLogic6 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic7 Iues	
Val	RisingEdge Zero IPatternArrayLogic6 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic7 Iues DontCare	
Val	RisingEdge Zero IPatternArrayLogic6 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic7 Iues DontCare EitherEdge	
Val	RisingEdge Zero IPatternArrayLogic6 Iues DontCare EitherEdge FallingEdge One RisingEdge Zero IPatternArrayLogic7 Iues DontCare EitherEdge FallingEdge FallingEdge FallingEdge	

Valu	PatternArrayLogic	8	Enum
Vait	ıes		
	DontCare		
	EitherEdge		
	FallingEdge		
	One		
	RisingEdge		
	Zero		
Digital	PatternArrayLogic	9	Enum
Valu	ıes		
	DontCare		
	EitherEdge		
	FallingEdge		
	One		
	RisingEdge		
	Zero		
MSxxD	igitalTriggerSet		Enum
			Enum
Desc	ription	e for all digital lines of Logic Pattern Trigger. Value can be Zero, One, Don't	Enum
Desc	cription Illows to select a value	e for all digital lines of Logic Pattern Trigger. Value can be Zero, One, Don't lling Edge or Either Edge.	Enum
Desc	cription Illows to select a value Care, Rising Edge, Fal		Enum
Desc	cription Illows to select a value Care, Rising Edge, Fal		Enum
Desc	cription Illows to select a value Care, Rising Edge, Falues Dontcare		Enum
Desc	cription Illows to select a value care, Rising Edge, Falues Dontcare EitherEdge		Enum
Desc	cription Allows to select a value care, Rising Edge, Falues Dontcare EitherEdge FallingEdge		Enum
Desc	cription Illows to select a value care, Rising Edge, Falues Dontcare EitherEdge FallingEdge One		Enum
Desc	cription Illows to select a value care, Rising Edge, Fallues Dontcare EitherEdge FallingEdge One RisingEdge		Enum
Desc	cription Illows to select a value care, Rising Edge, Falues Dontcare EitherEdge FallingEdge One		Enum
Desc A C Valu	cription Illows to select a value care, Rising Edge, Fallues Dontcare EitherEdge FallingEdge One RisingEdge		Enum
Desc A Valu	cription Illows to select a value care, Rising Edge, Falues Dontcare EitherEdge FallingEdge One RisingEdge Zero PigitalTriggerType		
Desc A Valu Valu Desc Desc	cription allows to select a value care, Rising Edge, Falues Dontcare EitherEdge FallingEdge One RisingEdge Zero DigitalTriggerType cription	lling Edge or Either Edge.	
Desc Valu Desc L	cription Illows to select a value care, Rising Edge, Falues Dontcare EitherEdge FallingEdge One RisingEdge Zero DigitalTriggerType cription ogic - permits creation		

Logic	
LogicBus	

PatternT	ype		Enum
Descri	otion		
		een Logic Pattern inputs. Note that only the "And" condition is available when	
any	digital input is in use. I	Note that mutiple digital edges are OR-combined.	
Value	•		
varac.	And		
	Nand		
	Nor		
	Or		
StateBot	tomArrayC1		Enum
Descri			
_		or one analog input of Logic Pattern Trigger. Value can be Low, High or	
	't Care.	one analog input of Logic Fattom ringgor. Value bar 20 Low, ringin of	
Value	5		
	High		
	Low		
StateBot	tomArrayC2		Enum
OtateBot	iomArayo2		
Value	5		
	High		
	Low		
StateBot	tomArrayC3		Enum
	-		
Value	5		
	High		
	Low		
StateBot	tomArrayC4		Enum
Value			
	High		
	Low		
StateBot	tomArrayExt		Enum
Value	5		
	High		
	Low		
MATH			app.Math

Variables of the form app.Math.xxxx control the mathematical functions F1 through F8.

Names of the form app.Math.Functions("Fx").xxxx are aliases of simpler names which are described in this section of the manual. Examples of alias pairs are as follows -

app.Math.Functions("Fx") is equivalent to app.Math.Fx

app.Math.Functions("Fx").Out.Result is equivalent to app.Math.Fx.Out.Result

app.Math.Functions("Fx").Zoom is equivalent to app.Math.Zoom.Fx

Please see under Acquisition. Channels for a programming example.

ClearSweeps	Action
ResetAll	Action
ShowZoomMenu	Action

ClearSweeps Action

Description

Clear sweeps for history functions such as average, histogram and trend. See also the general 'app.ClearSweeps' control which clears accumulated data for all subsystems, including persistence, measurement statistics, etc.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Clear sweeps for all history functions.
app.Math.ClearSweeps
```

ResetAll Action

Description

Reset the math subsystem to its default state.

All currently selected math operators, and other settings will be lost.

ShowZoomMenu Action

Description

Present the Zoom setup Menu (to setup the Zoom (Z) traces).

FUNCTIONS app.Math.Functions

Names of the form app.Math.Functions("Fx").xxxx are aliases of simpler names which are described in the section of the manual which is devoted to app.Math. Examples of alias pairs are as follows -

app.Math.Functions("Fx") is equivalent to app.Math.Fx

app.Math.Functions("Fx").Out.Result is equivalent to app.Math.Fx.Out.Result

app.Math.Functions("Fx").Zoom is equivalent to app.Math.Zoom.Fx

Please see under Acquisition. Channels for a programming example.

FX app.Math.Fx

This set of variables controls the math functions F1 through F8.

AxisXRotation	Integer
AxisYRotation	Integer

ClearSweeps	Action
DoResetZoom	Action
DoStoreToMemoryTrace	Action
Equation	String
LabelsPosition	String
LabelsText	String
MathMode	Enum
Operator1	Enum
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ShowLastTrace	Bool
Source1	Enum
UseGrid	String
View	Bool
ViewLabels	Bool

AxisXRotation Integer

Range From -90 to 90 step 1

Description

Sets/Queries the state of the X Axis rotation control, used only in 3d persistence modes to control the apparent viewing position. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
Set the rotation about the X-axis to 35 degrees for trace F3.
app.Acquisition.F3.AxisXRotation = 35
```

AxisYRotation Integer

Range From -90 to 90 step 1

Description

Sets/Queries the state of the Y Axis rotation control, used only in 3d persistence modes to control the apparent viewing position. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
Set the rotation about the Y-axis to 25 degrees for trace F3.
app.Acquisition.F3.AxisYRotation = 25
```

ClearSweeps Action

Description

Clears accumulated data for a single function trace.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Reset accumulation for trace F1 app.Math.F1.ClearSweeps

DoResetZoom Action

Description

Resets the zoom state of math trace Fx.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Reset zoom of math function F3. app.Math.F3.DoResetZoom

DoStoreToMemoryTrace

Action

Description

Store data from math function Fx to a memory trace. Destination for F1 will be M1, F2 will be M2, etc.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Store math function F2 to a memory trace.
app.Math.F2.DoStoreToMemoryTrace
```

Equation String

Range Any number of characters

Description

Queries the equation which defines the math function Fx.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Read the definition of math function F3. EquationF3 = app.Math.F3.Equation MsgBox EquationF3

Labels Position String

Range Any number of characters

Description

Sets / Queries the horizontal position of the label attached to the trace Fx. The unit of measurement is the unit of the horizontal scale. The measurement is made from the trigger point.

Note that this control is a string, not a numeric value. This allows multiple labels to be positioned, as shown in the example below.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Add a couple of labels to trace F1, one at Ons, and one at 55ns app.SetToDefaultSetup app.Math.F1.View = True app.Math.F1.ViewLabels = True app.Math.F1.LabelsPosition = "0.0, 55e-9" app.Math.F1.LabelsText = "Hello,World"
```

LabelsText String

Range Any number of characters

Description

Sets / Queries the text that appears in labels attached to acquisition trace Cx. Multiple labels may be specified by using comma as a delimiter. See the documentation on LabelsPosition for an example of use.

MathMode Enum

Description

Sets/Queries the math mode.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the mode of the math function F1
app.Math.F1.MathMode = "TwoOperators"
```

Graphing	Graphing mode, chain a measurement and a graphing operator
OneOperator	Single math operator
TwoOperators	Chain two math operators
WebEdit	

Operator1 Enum

Description

Sets/Queries the first operator of math function Fx. When MathMode = "OneOperator, this is the only math operator, when MathMode = "TwoOperator", this is the first of two operators. Note that when MathMode = "Graph", this control has no effect.

Note also that the list of available math operators varies depending upon the instrument model number, and the list of installed software options.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Define the first operator of math function F1 as an Average app.Math.F1.View = True app.Math.F1.MathMode = "OneOperator" app.Math.F1.Operator1 = "Average"
```

AbsoluteValue	
Average	
Boxcar	
Сору	
Correlation	
Demodulate	
Derivative	
Deskew	
Difference	
EnhancedResolution	
Envelope	
ExcelMath	
Ехр	
Exp10	
FastWavePort	
FFT	
Filter	
Floor	
Histogram	
Htie2BER	
I2SToWform	
Integral	
Interpolate	
Invert	
ISIPatt	
Ln	
Log10	
LowPassIIR	
MathcadMath	
MATLABWaveform	
Null	

PersistenceHistogram	
PersistenceTraceMean	
PersistenceTraceRange	
PersistenceTraceSigma	
Product	
Ratio	
Reciprocal	
Reframe	
Rescale	
Roof	
SegmentSelect	
SeqBuilder	
SequenceAverage	
SinXOverX	
Sparse	
Square	
SquareRoot	
Sum	
Track	
Trend	
Trk	
WaveScript	
Zoom	

Persist3DQuality Enum

Description

Sets/Queries the state of the 3D Persistence quality control. Control the way that the persistence trace is rendered. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set persistence 3-D to shaded for trace F1
app.Math.F1.Persist3DQuality = "Shaded"
```

Shaded	
Solid	
WireFrame	

Persisted Bool

Description

Sets/Queries the persisted state of the function waveform. If the Display.LockPersistence control is set to 'AllLocked' then the persisted state of all displayed waveforms will be the same. If the Display.LockPersistence control is set to 'PerTrace' then the persisted state of each waveform may be independently controlled.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set persistence on for trace F3.
app.Math.F3.Persisted = True
```

Persistence3d Bool

Description

Sets/Queries the 3D persistence state. If True, then the persistence display for this channel will be displayed as a three dimensional surface map. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
Set persistence plot as 3-D for trace F4.
app.Acquisition.F4.Persistence3D = True
```

PersistenceMonoChrome

Bool

Description

Sets/Queries the monochrome persistence state. If True, then the persistence display for this channel will be monochromatic, whether 2-D or 3-D.

See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set persistence monochrome on for trace F1
app.Math.F1.PersistenceMonoChrome = True
```

PersistenceSaturation

Integer

Range From 0 to 100 step 1

Description

Sets/Queries the saturation threshold for persisted waveforms. All information at this level or above will be recorded with the same color or intensity. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the persistence saturation level for trace F1.
app.Math.F1.PersistenceSaturation = 40
```

PersistenceTime Enum

Description

Sets/Queries the state of the Persistence Time control. Controls the persistence decay time for this trace. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the persistence time for the trace F1 to 10 seconds.
app.Math.F1.PersistenceTime = "10s"
```

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

ShowLastTrace Book

Description

Sets/Queries the state of the Show Last Trace control. If True then when this trace is displayed in persistence mode the last acquired waveform will be superimposed on the accumulating persistence map. See the general description above for a discussion of the locked and unlocked persistence modes.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Do not show the last trace for the persistence trace of trace F1.
app.Math.F1.ShowLastTrace = False
```

Source1 Enum

Description

Sets/Queries the first source of the first operator in Fx. Note that the two possible sources of Operator1 are Source1 and Source2, Source3 is the second source to Operator2, with the first source of Operator2 being the ouput of Operator1.

Note that the list of available sources is dependent upon the instrument model, and it's installed software options.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Define the first source of math function F1 as C3.
app.Math.F1.Source1 = "C3"
```

BadBits	
BadBits2	
Bits	
Bits2	
C1	
C2	
C3	
C4	
Decode1	
Decode2	
Decode3	
Decode4	
Digital1	
Digital2	
Digital3	
Digital4	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye	
Eye2	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
Harm	
ı	

M1 M2 M3 M4 Mod P1 P2 P3 P4 P5 P6 P7 P8 PointA PointB PointC PointD PointF	
M3 M4 Mod P1 P2 P3 P4 P5 P6 P7 P8 PointA PointC PointD	
M4 Mod P1 P2 P3 P4 P5 P6 P7 P8 PointA PointC PointD	
Mod P1 P2 P3 P4 P5 P6 P7 P8 PointA PointC PointD	
P1 P2 P3 P4 P5 P6 P7 P8 PointA PointB PointD	
P2 P3 P4 P5 P6 P7 P8 PointA PointC PointD	
P3 P4 P5 P6 P7 P8 PointA PointB PointC PointD	
P4 P5 P6 P7 P8 PointA PointB PointC PointD	
P5 P6 P7 P8 PointA PointB PointC PointD	
P6 P7 P8 PointA PointB PointC PointD	
P7 P8 PointA PointB PointC PointD	
P8 PointA PointB PointC PointD	
PointA PointB PointC PointD	
PointB PointC PointD	
PointC PointD	
PointD	
DeletE	
Pointe	
PointH	
PRBS	
Pwr	
R	
ScanHisto	
ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	
V	
Z1	
Z2	
Z3	
Z4	
Z5	
Z6	
Z7	
Z8	

UseGrid String

Range Any number of characters

Description

Sets/Queries the grid in use for the math trace Fx. See also app.Acquisition.Cx.UseGrid.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Place math trace F3 on grid YT4.
app.Math.F3.UseGrid = "YT4"
```

View Bool

Description

Sets/Queries whether the trace of math function Fx is visible. Note that even when math traces are not visible, but are being used as inputs to other math functions and/or measurements, they are computed.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Show math trace F3.
app.Math.F3.View = True
```

ViewLabels Book

Description

Sets/Queries whether trace labels, defined with LabelsText and LabelsPosition controls, are shown.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Show the user-defined trace label for trace F1
app.Math.F1.ViewLabels = True
```

OPERATOR1SETUP

app.Math.Fx.Operator1Setup

This node is dynamically created, and will contain the controls for the operator currently selected into Operator1. See the Math/Measure Control reference at the end of this manual for a lost of these controls.

RESULT

app.Math.Fx.Out.Result

Properties of the type xxxx.Out.Result.yyyy are those of the last completed acquisition. They are not affected if other cvars are changed after that acquisition was completed. This distinction between "Out.Result" properties and other cvars is most important when the trigger mode is Single or Stopped. You should treat "Out.Result" properties as read-only.

For a detailed description of all properties available for the output of a Math Function, please see Chapter 1.

ZOOM app.Math.Fx.Zoom

This set of variables controls the zoom functions for math trace Fx.

CenterSelectedSegment	Integer
HorPos	Double
HorZoom	Double
NumSelectedSegments	DoubleLockstep
VariableHorZoom	Bool
VariableVerZoom	Bool
VerPos	Double
VerZoom	Double

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Turn on trace F1, will default to Zoom-Only
app.Math.F1.View = True
app.Math.F1.Source1 = "C1"
```

' Zoom trace F1 by a factor of 2 horizontally and vertically app.Math.F1.Zoom.Rese

CenterSelectedSegment

Integer

Range From 1 to 1 step 1

HorPos Double

Range From -0.5 to 0.5 step (8 digits)

Description

Sets/Queries the horizontal position of center of the grid on the zoomed trace Fx. The unit of measurement is the screen width, that is, 0.3 means a shift of three of the ten divisions. A positive value moves the trace to the left.

HorZoom Double

Range From 0.1 to 1e+006 step (8 digits)

Description

Sets/Queries the horizontal magnification of the trace Fx. The magnification will be in a 1 2 5 10 sequence unless variable horizontal magnification has been set.

NumSelectedSegments

DoubleLockstep

Range From 1 to 1 step 1, locked to 1 2 5, fine grain allowed=true, on=false

VariableHorZoom Bool

Description

Sets/Queries the ability to zoom horizontally by a continuously variable factor. Note that if a horizontal zoom of 0.9 is set, while variable zoom is off, the horizontal zoom will be set to 1.0. If the variable zoom is then enabled, the factor of 0.9 will have been remembered, and it will be used. Note that the previous value will not be remembered during a power-cycle.

Variable Ver Zoom Bool

Description

Sets/Queries the ability to zoom vertically by a continuously variable factor. Note that if a vertical zoom of 0.9 is set, while variable zoom is off, the vertical zoom will be set to 1.0. If the variable zoom is then enabled, the factor of 0.9 will have been remembered, and it will be used. Note that the previous value will not be remembered during a power-cycle.

VerPos Double

Range From -1.5 to 1.5 step (8 digits)

Description

Sets/Queries the vertical position of center of the grid on the zoomed trace Fx. The unit of measurement is the screen height, that is, 0.375 means a shift of three of the eight divisions. A positive value moves the trace downwards.

VerZoom Double

Range From 0.1 to 100 step (8 digits)

Description

Sets/Queries the vertical magnification of the trace Fx. The magnification will be in a 1 2 5 10 sequence unless VariableVerZoom has been set to True, in which case it will be continuously variable.

XY app.Math.XY

This set of variables controls the display of data in X vs. Y mode. Only Valid when the instrument is in XY, XYSingle, or XYDual display modes.

AxisXRotation	Integer
AxisYRotation	Integer
ClearSweeps	Action
InputX	Enum
InputY	Enum
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ShowLastTrace	Bool

Example

' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

```
' Switch to XY+Dual Grid Mode
app.Display.GridMode = "XYDual"

' Configure XY to show C1 vs. C2 in 3D Persistence mode
app.Math.XY.InputX = "C1"
app.Math.XY.InputY = "C2"
app.Math
```

AxisXRotation Integer

Range From -90 to 90 step 1

Description

Sets/Queries the state of the X Axis rotation control, used only in 3-D persistence modes to control the viewing position. See the general description above for a discussion of the locked and unlocked persistence modes.

AxisYRotation Integer

Range From -90 to 90 step 1

Description

Sets/Queries the state of the Y Axis rotation control, used only in 3-D persistence modes to control the viewing position. See the general description above for a discussion of the locked and unlocked persistence modes.

ClearSweeps Action

Description

Clears persistence X-Y plot.

InputX Enum

Description

Sets/Queries the name of the input channel for the X axis of the X-Y plot.

BadBits	
BadBits2	
Bits	
Bits2	
C1	
C2	
C3	
C4	
Digital1	
Digital2	
Digital3	
Digital4	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye	
Eye2	
F1	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
Harm	
I	
M1	
M2	
M3	
M4	
Mod	
PointA	
PointB	
PointC	
PointD	
PointF	
PointH	
PRBS	
_	

Pwr	
R	
ScanHisto	
ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	
V	
Z1	
Z2	
Z3	
Z4	
Z5	
Z6	
Z7	
Z8	

InputY Enum

Description

Sets/Queries the name of the input channel for the Y axis of the X-Y plot.

BadBits	
BadBits2	
Bits	
Bits2	
C1	
C2	
C3	
C4	
Digital1	
Digital2	
Digital3	
Digital4	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye	
Eye2	
F1	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
Harm	
1	
M1	
M2	
M3	
M4	
Mod	
PointA	
PointB	
PointC	
PointD	
PointF	
PointH	
PRBS	

Pwr	
R	
ScanHisto	
ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	
V	
Z1	
Z2	
Z3	
Z4	
Z 5	
Z6	
Z7	
Z8	

Persist3DQuality Enum

Description

Sets/Queries the state of the 3D Persistence quality control. Controls the way that the persistence trace is rendered. See the general description above for a discussion of the locked and unlocked persistence modes.

Values

Shaded	
Solid	
WireFrame	

Persisted Bool

Description

Sets/Queries the persisted state of the X-Y plot. If the Display.LockPersistence control is set to 'AllLocked' then the persisted state of all displayed waveforms will be the same. If the Display.LockPersistence control is set to 'PerTrace' then the persisted state of each waveform may be independently controlled.

Persistence3d Bool

Description

Sets/Queries the 3D persistence state. If True, then the persistence display for the X-Y plot will be displayed as a three dimensional surface map.

See the general description above for a discussion of the locked and unlocked persistence modes.

PersistenceMonoChrome

Bool

Description

Sets/Queries the monochrome persistence state. If True, then the persistence display for the X-Y plot will be monochromatic, whether 2-D or 3-D. See the general description above for a discussion of the locked and unlocked persistence modes.

PersistenceSaturation Integer

Range From 0 to 100 step 1

Description

Sets/Queries the saturation threshold for persisted X-Y plot. All information at this level or above will be recorded with the same color or intensity. See the general description above for a discussion of the locked and unlocked persistence modes.

PersistenceTime Enum

Description

Sets/Queries the state of the Persistence Time control. Controls the persistence decay time for the Xy persistence. See the general description above for a discussion of the locked and unlocked persistence modes.

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

ShowLastTrace Book

Description

Sets/Queries the state of the Show Last Trace control. If True then when this trace is displayed in persistence mode the last acquired waveform will be superimposed on the accumulating persistence map.

See the general description above for a discussion of the locked and unlocked persistence modes.

RESULT app.Math.XY.Out.Result

Properties of the type xxxx.Out.Result.yyyy are those of the last completed acquisition. They are not affected if other cvars are changed after that acquisition was completed. This distinction between "Out.Result" properties and other cvars is most important when the trigger mode is Single or Stopped. You should treat "Out.Result" properties as read-only.

Note that this XY result object is very similar, but not identical to the result object exposed by the channel and math traces. The differences are due to the fact that the XY trace returns pairs of data values, one for X, one for Y.

For a detailed description of all properties available for the output of an XY trace, please see Chapter 1.

MEASURE app.Measure

Variables of the form app. Measure control the parameters P1 through P8, and their associated statistical results and histicons.

Names of the forms app.Measure.Measure("Premote").xxxx and app.Measure.Measure("Px").xxxx are aliases of simpler names which are described in this section of the manual. Examples of alias pairs are as follows -

app.Measure.Measure("Premote").OutResult is equivalent to app.Measure."Premote".OutResult app.Measure.Measure("Px").Statistics is equivalent to app.Measure.Px.Statistics
Please see under Acquisition.Channels for a programming example.

ClearAll	Action
ClearAllHelpMarkers	Action
ClearSweeps	Action
HelpMarkers	Enum
HistoOn	Bool
MeasureSet	Enum
SetGateToDefault	Action
ShowAllHelpMarkers	Action
ShowMeasure	Bool
StatsOn	Bool
StdGateStart	Double
StdGateStop	Double
StdSource	Enum

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'get into the custom parameter mode
app.Measure.MeasureMode = "MyMeasure"
app.Measure.ClearAll
app.Measure.StatsOn = True
app.Measure.HistoOn = False

'Configure P1 to measure a
```

Clear All Action

Description

Resets all parameter setups, turning each of the parameters view to "off", the MeasurementType to "measure" and the selected paramEngine to "Null".

ClearAllHelpMarkers

Action

Description

Force all 'HelpMarkers' off.

(HelpMarkers are the on-trace annotation of measurement setup and results)

ClearSweeps Action

Description

Clears the accumulated statistics for parametersP1 to P8 as well as the acumulated statistics for their associated histicons.

HelpMarkers Enum

Description

Sets/Queries the level of detail for help markers (if indeed any of the selected parameter definitions have help markers).

These markers are displayed on the source traces, and only if those traces are viewed simultaneously with the parameter measurements.

Note: this setting is global for all Px

Values

Detailed	Detailed help markers
Off	No help markers
Simple	Simple help markers

HistoOn Bool

Description

Sets/Queries the visibility of the histicons of the parameters which are viewed.

MeasureSet Enum

Description

Defines the mode in which the measurement system is working.

Values

MyMeasure	Custom list, each chosen from the list of available measurements.
StdHorizontal	Standard Horizontal Measurements
StdVertical	Standard Vertical Measurements

SetGateToDefault Action

Description

Sets the measure gate to its default state. Valid only when in either Std. Vertical or Std. Horizontal measurement modes. For MyMeasure see the equivalent controls under Px.

ShowAllHelpMarkers

Action

Description

Force all 'HelpMarkers' on.

(HelpMarkers are the on-trace annotation of measurement setup and results)

ShowMeasure Bool

Description

Defines whether the measure results table is displayed or not.

StatsOn Bool

Description

Sets/Queries the visibility of parameter statistics. Note: the statistics are accumulated whether the view of them is on or not, so you needn't have StatsOn = "On" to collect statistics.

StdGateStart Double

Range From 0 to 10 step 0.01

Description

Sets/Queries the position of the left hand limit of the measure gate (n divisions). Valid only when in either Std. Vertical or Std. Horizontal measurement modes. For MyMeasure see the equivalent controls under Px.

StdGateStop Double

Range From 0 to 10 step 0.01

Description

Sets/Queries the position of the right hand limit of the measure gate (in divisions). Valid only when in either Std. Vertical or Std. Horizontal measurement modes. For MyMeasure see the equivalent controls under Px.

StdSource Enum

Description

Sets/Queries the channel which is the source of ALL standard voltage or time parameters. Note that when in 'My Measure' mode each parameter has it's own Source selection, and this setting is ignored.

BadBits	
BadBits2	
Bits	
Bits2	
C1	
C2	
C3	
C4	
D0	
D1	
D10	
D11	
D12	
D13	
D15	
D16	
D17	
D18	
D19	
D2	
D20	
D21	
D22	
D23	
D24	
D25	
D26	
D27	
D28	
D29	
D3	
D30	
D31	
D32	
D33	
D34	
D35	
D4	
D5	

D6	
D7	
D8	
D9	
Decode1	
Decode2	
Decode3	
Decode4	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye	
Eye2	
F1	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
FLXEye	
Harm	
1	
M1	
M2	
M3	
M4	
Mod	
PointA	
PointB	
PointC	
PointD	
PointF	
PointH	
PRBS	
Pwr	
R	
ScanHisto	
ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	

V	
Z1	
Z2	
Z3	
Z4	
Z5	
Z6	
Z7	
Z8	

MEASURE app.Measure.Measure

Names of the forms app.Measure.Measure("Premote").xxxx and app.Measure.Measure("Px").xxxx are aliases of simpler names which are described in the section of the manual which is devoted to app.Measure. Examples of alias pairs are as follows -

app.Measure.Measure("Premote").OutResult is equivalent to app.Measure."Premote".OutResult app.Measure.Measure("Px").Statistics is equivalent to app.Measure.Px.Statistics

Please see under app.Acquisition.Channels("Cx") for a programming example.

RESULT	app.Measure.PRemote.histo.Result
RESULT	app.Measure.PRemote.last.Result
RESULT	app.Measure.PRemote.max.Result
RESULT	app.Measure.PRemote.mean.Result
RESOLI	
RESULT	app.Measure.PRemote.min.Result
RESULT	app.Measure.PRemote.num.Result

RESULT

app.Measure.PRemote.sdev.Result

STATISTICS

app.Measure.PRemote.Statistics

PX app.Measure.Px

This set of variables controls the parameters P1 through P8, (when the MeasureMode is "MyMeasure", otherwise these are predefined) and the statistical results and histicons which depend on them.

FindLevel	Action
FindRange	Action
GateByRange	Bool
GateByWform	Bool
GateStart	Double
GateStop	Double
HelpAlwaysOn	Bool
LevelType	Enum
LowerLimit	Double
MeasurementType	Enum
ParamEngine	Enum
PassWhen	Enum
PercentLevel	Double
Source1	Enum
UpperLimit	Double

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
app.Measure.MeasureMode = "MyMeasure"
' Set parameter P1 to math on parameters.
App.Measure.P1.MeasurementType = "math"
```

FindLevel Action
FindRange Action

GateByRange Book

Description

If True, only measurements who's value(s) fall between the limits defined by the LowerLimit and UpperLimit controls, are accepted.

GateByWform Bool

Description

If True, measurements are gated by the state of the waveform defined by the WformSource control.

GateStart Double

Range From 0 to 10 step 0.01

Description

Sets/Reads the position of the left hand edge of the measure gate for parameter Px.

GateStop Double

Range From 0 to 10 step 0.01

Description

Sets/Reads the position of the right hand edge of the measure gate for parameter Px.

HelpAlwaysOn Bool

Description

Defines whether Help Marters are always displayed for this measurement, even when the measurement dialog is closed.

LevelType Enum

Values

Absolute	
Percent	

LowerLimit Double

Range From -1e+010 to 1e+010 step (4 digits)

MeasurementType Enum

Description

Sets/Queries the measurement type of the parameter Px.

math	Measurement is a mathematical combination of one or two other Py,Pz
measure	Standard measurement mode (parametric of a trace waveform)
WebEdit	Measurement is defined using the Processing Web Editor

ParamEngine Enum

Description

Sets/Queries the parameter (measurement on a trace) for Px. This setting applies only if the MeasurementType control is set to "measure".

100BTfall	
100BTrise	
100BTTIE	
100BTTj	
10BTH	
10BTJ	
Amplitude	
AmplitudeAsymmetry	
Analog2Protocol	
ApparentPower	
Area	
AutoCorrelationSignalTo	
Base	
BurstWidth	
CANLoad	
CANMsgBR	
CANMsgNum	
CANtoAnalog	
CANtoCAN	
CANtoValue	
Cycles	
Delay	
DeltaDelay	
DeltaMessages	
DeltaPeriodAtLevel	
DeltaTimeAtLevel	
DeltaTriggerTime	
DeltaWidthAtLevel	
DOV	
Duration	
DutyAtLevel	
DutyCycle	
DutyCycleDistortion	
EdgeAtLevel	
EMClvlPulse	
EMCt2Val	
EOvshN	
EOvshP	
ExcelParam	
ExtinctionRatio	
L	

EyeAmplitude	
EyeAvgPower	
EyeBER	
EyeCrossing	
EyeHeight	
EyeOneLevel	
EyeQFactor	
EyeWidth	
EyeZeroLevel	
Fall	
Fall8020	
FallAtLevel	
FastMultiWPort	
FirstPoint	
Frequency	
FrequencyAtLevel	
FullWidthAtHalfMaximum	
FullWidthAtXX	
GapWidth	
GBM1FGDroop	
GBM1HJDroop	
HalfPeriod	
HistogramAmplitude	
HistogramBase	
HistogramMaximum	
HistogramMean	
HistogramMedian	
HistogramMid	
HistogramMinimum	
HistogramRms	
HistogramSdev	
HistogramTop	
HoldTime	
HParamScript	
I2StoValue	
LastPoint	
LevelAtX	
LocalBase	
LocalBaselineSeparation	
LocalMaximum	
LocalMinimum	
LocalNumber	
LocalPeakToPeak	
LocalTimeAtMaximum	
LocalTimeAtMinimum	
LocalTimeBetweenEvent	

LocalTimeBetweenPeaks	
LocalTimeBetweenTroug	
LocalTimeOverThreshold	
LocalTimePeakToTrough	
LocalTimeTroughToPeak	
LocalTimeUnderThreshol	
MathcadParam	
MATLABParameter	
Maximum	
MaximumPopulation	
Mean	
Median	
Minimum	
Mode	
NarrowBandPhase	
NarrowBandPower	
NCycleJitter	
NonLinearTransitionShift	
npoints	
Null	
NumberOfModes	
OvershootNegative	
OvershootPositive	
Overwrite	
ParamScript	
PEAKMAG	
Peaks	
PeakToPeak	
Percentile	
Percentile	
Percentile Period	
Percentile Period PeriodAtLevel	
Percentile Period PeriodAtLevel Phase	
Percentile Period PeriodAtLevel Phase PopulationAtX	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor Protocol2Analog	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor Protocol2Analog Protocol2Protocol	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor Protocol2Analog Protocol2Protocol Protocol2Value ProtocolBitrate ProtocolLoad	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor Protocol2Analog Protocol2Protocol Protocol2Value ProtocolBitrate	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor Protocol2Analog Protocol2Protocol Protocol2Value ProtocolBitrate ProtocolLoad	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor Protocol2Analog Protocol2Protocol Protocol2Value ProtocolBitrate ProtocolLoad ProtocolNumMessages	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor Protocol2Analog Protocol2Protocol Protocol2Value ProtocolBitrate ProtocolLoad ProtocolNumMessages PW50	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor Protocol2Analog Protocol2Protocol Protocol2Value ProtocolBitrate ProtocolLoad ProtocolNumMessages PW50 PW50Negative	
Percentile Period PeriodAtLevel Phase PopulationAtX PowerFactor Protocol2Analog Protocol2Protocol Protocol2Value ProtocolBitrate ProtocolLoad ProtocolNumMessages PW50 PW50Negative PW50Positive	

Rise	
Rise2080	
RiseAtLevel	
RootMeanSquare	
SAS	
Setup	
Skew	
Slew	
StandardDeviation	
TAA	
TAANegative	
TAAPositive	
TIE	
TimeAtCAN	
TimeAtLevel	
TimeAtProtocol	
Тор	
TotalPopulation	
tUpS	
Width	
WidthAtLevel	
WidthNegative	
XAtMaximum	
XAtMinimum	
XAtPeak	

PassWhen Enum

Values

High	
Low	

PercentLevel Double

Range From 0 to 100 step 1

Source1 Enum

Description

Sets/Queries the first trace source of the parameter Px. Used only when MeasurementType = "measure", for MeasurementType = "math", refer to PSource1.

BadBits2	
Bits2	
C1	
C2	
C3	
C4	
D0	
D1	
D10	
D11	
D12	
D13	
D14	
D15	
D16	
D17	
D18	
D19	
D2	
D20	
D21	
D22	
D23	
D24	
D25	
D26	
D27	
D28	
D29	
D3	
D30	
D31	
D32	
D33	
D34	
D35	
D4	
D5	
D6	
D7	

D8	
D9	
Decode1	
Decode2	
Decode3	
Decode4	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye2	
F1	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
FLXEye	
Harm	
1	
M1	
M2	
M3	
M4	
Mod	
PointA	
PointB	
PointC	
PointD	
PointF	
PointH	
Pwr	
R	
ScanHisto	
ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	
V	
Z1	
Z2	
Z3	

Z4	
Z5	
Z6	
Z7	
Z8	

UpperLimit Double

Range From -1e+010 to 1e+010 step (4 digits)

RESULT app.Measure.Px.histo.Result

RESULT app.Measure.Px.last.Result

RESULT app.Measure.Px.max.Result

RESULT app.Measure.Px.mean.Result

RESULT app.Measure.Px.min.Result

RESULT app.Measure.Px.num.Result

OPERATOR app.Measure.Px.Operator

This path specifies that the selected ParamEngine or ArithEngine control variables are "here"

RESULT app.Measure.Px.Out.Result

Properties of the type xxxx.Out.Result.yyyy are those of the last completed acquisition. They are not affected if other

cvars are changed after that acquisition was completed. This distinction between "Out.Result" properties and other cvars is most important when the trigger mode is Single or Stopped. You should treat "Out.Result" properties as read-only.

RESULT

app.Measure.Px.sdev.Result

STATISTICS

app.Measure.Px.Statistics

This set of variables controls the statistical summaries that are provided for all the parameters.

MEMORY app.Memory

Variables of the form app. Memory. xxxx control the memories M1 through M4.

Names of the form app.Memory.Memories("Mx").xxxx are aliases of simpler names which are described in this section of the manual. Examples of alias pairs are as follows -

app.Memory.Memories("Mx").Out.Result is equivalent to app.Memory.Mx.Out.Result app.Memory.Memory.Mx.Zoom is equivalent to app.Memory.Mx.Zoom

Please see under app.Acquisition.Channels("Cx") for a programming example.

Clear All Mem Action

Description

Clears the contents of all trace memories.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Clear the contents of all trace memories.
app.Memory.ClearAllMem
```

MEMORIES

app.Memory.Memories

Names of the form app.Memory.Memories("Mx").xxxx are aliases of simpler names which are described in the section of the manual which is devoted to app.Memory. Examples of alias pairs are as follows - app.Memory.Memories("Mx").Out.Result is equivalent to app.Memory.Mx.Out.Result app.Memory.Memories("Mx").Zoom is equivalent to app.Memory.Mx.Zoom

Please see under Acquisition.Channels for a programming example.

MX

app.Memory.Mx

This set of variables controls the memories M1 through M4.

ClearMem	Action
Сору	Action
LabelsPosition	String
LabelsText	String
Source1	Enum
UseGrid	String
UserText	String
View	Bool
ViewLabels	Bool

ClearMem Action

Description

Initiates a clear memory operation for memory Mx.

Copy Action

Description

Copy the trace specified by the Source1 control into this memory.

Labels Position String

Range Any number of characters

Description

Sets / Queries the horizontal position of the label attached to the acquisition trace Cx. The unit of measurement is the unit of the horizontal scale. The measurement is made from the trigger point. Note that this control is a string, not a numeric value. This allows multiple labels to be positioned, as shown in the example below.

LabelsText String

Range Any number of characters

Source1 Enum

Description

Source trace for Copy operations (see 'Copy' control)

BadBits	
BadBits2	
Bits	
Bits2	
C1	
C2	
C3	
C4	
Digital1	
Digital2	
Digital3	
Digital4	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye	
Eye2	
F1	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
Harm	
1	
M2	
M3	
M4	
Mod	
PointA	
PointB	
PointC	
PointD	
PointF	
PointH	
PRBS	
Pwr	

R	
ScanHisto	
ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	
V	
Z1	
Z2	
Z3	
Z4	
Z5	
Z6	
Z7	
Z8	

UseGrid String

Range Any number of characters

Description

Sets/Queries the grid used for memory trace Mx.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Set memory trace M2 to use grid YT3. app.Memory.M2.UseGrid = "YT3"

UserText String

Range Any number of characters

Description

Text field, used to attach arbitrary comments to a memory waveform.

View Bool

Description

Sets/Queries whether memory trace Mx is visible.

ViewLabels Bool

Description

Sets/Queries whether labels are visible for trace Mx.

RESULT

app.Memory.Mx.Out.Result

See app.Acquisition.Cx.Out.Result for a definition of methods and properties used to access the Mx waveform result.

ZOOM app.Memory.Mx.Zoom

This set of variables controls zooming of the memory traces M1 through M4.

CenterSelectedSegment	Integer
HorPos	Double
HorZoom	Double
NumSelectedSegments	DoubleLockstep
VariableHorZoom	Bool
VariableVerZoom	Bool
VerPos	Double
VerZoom	Double

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Save C1 into M1
app.SaveRecall.Waveform.SaveTo = "Memory"
app.SaveRecall.Waveform.SaveSource = "C1"
app.SaveRecall.Waveform.SaveDestination = "M1"
app.SaveRecall.Waveform.DoSave
```

CenterSelectedSegment

Integer

Range From 1 to 1 step 1

HorPos Double

Range From -0.5 to 0.5 step (8 digits)

Description

Sets/Queries the horizontal position of center of the grid on the zoomed trace Mx. The unit of measurement is the screen width, that is, 0.3 means a shift of three of the ten divisions. A positive value moves the trace to the left.

HorZoom Double

Range From 0.1 to 1e+006 step (8 digits)

Description

Sets/Queries the horizontal magnification of the trace Mx. The magnification will be in a 1 2 5 10 sequence unless variable horizontal magnification has been set.

NumSelectedSegments

DoubleLockstep

Range From 1 to 1 step 1, locked to 1 2 5, fine grain allowed=true, on=false

VariableHorZoom Bool

Description

Sets/Queries the ability to zoom horizontally by a continuously variable factor as opposed to a factor that follows a 1, 2, 5 sequence.

VariableVerZoom Bool

Description

Sets/Queries the ability to zoom vertically by a continuously variable factor as opposed to a factor that follows a 1, 2, 5 sequence.

VerPos Double

Range From -1.5 to 1.5 step (8 digits)

Description

Sets/Queries the vertical position of center of the grid on the zoomed trace Mx. The unit of measurement is the screen height, that is, 0.375 means a shift of three of the eight divisions. A positive value moves the trace downwards.

VerZoom Double

Range From 0.1 to 100 step (8 digits)

Description

Sets/Queries the vertical magnification of the trace Mx. The magnification will be in a 1 2 5 10 sequence unless variable vertical magnification has been set.

PASSFAIL app.PassFail

Names of the forms app.PassFail("Qremote").xxxx and app.PassFail("Qx").xxxx are aliases of simpler names which are described in this section of the manual. Examples of alias pairs are as follows -

app.PassFail.PassFail("Qremote").Operator is equivalent to app.PassFail.Qremote.Operator app.PassFail.PassFail("Qx").Out.Result is equivalent to app.PassFail.Qx.Out.Result Please see under app.Acquisition.Channels("Cx") for a programming example.

ActionOn	Enum
Alarm	Bool
EnableActions	Bool
PredefinedConditions	Enum
PrintScreen	Bool
Pulse	Bool
Save	Bool
Stop	Bool
StopAfter	Integer
StopTesting	Bool
SummaryView	Bool
Testing	Bool

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Setup Parameter P1 to be the amplitude of C1
app.Measure.MeasureMode = "MyMeasure"
app.Measure.P1.ParamEngine = "Ampl"
app.Measure.P1.Source1 = "C1"
app.Measure.P1.View = True
```

ActionOn Enum

Value	es		
	Fail		
	Pass		
Alarm			Bool
	ription ets/Queries whether Alar	m is included in the PassFail actions.	
Enable/	Actions		Bool
Dogge	intina		
	ription	selected actions will be executed if the selected PassFail condition is met.	
		selected actions will be executed if the selected rassi all condition is met.	
Predefin	nedConditions		Enum
Se Ar		iteria that must be met in a pass-fail test. For example, the condition ass-fail criterion is met if at least one of the test conditions results in a True	
Value	es		
	AllFalse		
	AllQ1ToQ4OrAllQ5ToQ8		
	AllTrue		
	AnyFalse		
	AnyQ1ToQ4AndAnyQ5T		
	AnyTrue		
PrintSc	reen		Bool
	ription ets/Queries whether Prin	t Screen is included in the PassFail actions.	
Pulse			Bool
Descr	iption		
Se	•	se is included in the PassFail actions. This action emits a pulse from the Aux	(
Save			Bool
	ription	o is included in the Desc Foil actions	
56	ets/Queries whether Sav	e is included in the PassFail actions.	
Ston			Bool

Description

Sets/Queries whether Stop is included in the PassFail actions.

StopAfter Integer

Range From 1 to 1000000000 step 1

Description

Sets/Queries the maximum number of sweeps that will be acquired before testing is halted.

StopTesting Book

Description

If Enabled, testing will stop after a number of sweeps defined by the StopAfter control.

Summary View Book

Description

Summary view

Testing Book

Description

Sets/Queries whether PassFail testing is on.

RESULT

app.PassFail.LastPass.Result

RESULT

app.PassFail.NumPassed.Result

QX app.PassFail.Qx

This set of variables controls the tests Q1 through Q8 in the pass fail system.

ClearSweeps	Action
ConditionEngine	Enum
Equation	String
PSource1	Enum
ShortDescription	String
View	Bool
WSource2	Enum

ClearSweeps Action

Description

ClearSweeps

ConditionEngine	Enui
ConditionEngine	Enui

Description

Sets/Queries whether pass-fail test Qx uses mask testing or parameter comparison.

Values

BoolPassThru	
DualParamCompare	
MaskTestCondition	
ParameterCompare	

Equation String

Range Any number of characters

Description

Inspects the equation for pass-fail test Qx. A typical equation would be "All P3 < 0.7071".

PSource1 Enum

Description

PSource1

AvgAB	
ClkJit	
DOVN	
DOVP	
DroopFG	
DroopHJ	
Dstr	
DtaJit	
E10BTHarm	
E10BTPeak	
E85BTJit	
E8BTJit	
EDCD	
FitMasks	
FLXAsymDelay	
FLXAsymDelay	
FLXFrameTSSLengthCa	
FLXFrameTSSLengthCa	
FLXJitter	
FLXJitter	
FLXPropDelay	
FLXPropDelay	
LFall	
LRise	
Mask2Hits	
Mask2Out	
MaskHits	
MaskOut	
MaxRF	
MinRF	
NonMonotonic	
OverN	
OverP	
P1	
P2	
P3	
P4	
P5	
P6	
P7	
P8	

PeakMagA	
PeakMagB	
PeakMagC	
PeakMagD	
PkPkClkJit	
PkPkDtaJit	
PkPkFiltJit	
PkPkFiltSlv	
PkPkSlaveJit	
PkPkSlvDta	
SAS	
SlaveJit	
TIE	
TotJitN	
TotJitP	
UFall	
URise	

ShortDescription String

Range Any number of characters

Description

ShortDescription

View Book

Description

Sets/Queries whether pass-fail test Qx is visible.

WSource2 Enum

Description

WSource2

BadBits	
BadBits2	
Bits	
Bits2	
C1	
C2	
C3	
C4	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye	
Eye2	
F1	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
FLXEye	
Harm	
I	
M1	
M2	
M3	
M4	
Mod	
PointA	
PointB	
PointC	
PointD	
PointF	
PointH	
PRBS	
Pwr	
R	
ScanHisto	

ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	
V	
Z1	
Z2	
Z3	
Z4	
Z5	
Z6	
Z 7	
Z8	

RESULT

app.PassFail.Qx.Out.Result

Properties of the type xxxx.Out.Result.yyyy are those of the last completed acquisition. They are not affected if other cvars are changed after that acquisition was completed. This distinction between "Out.Result" properties and other cvars is most important when the trigger mode is Single or Stopped. You should treat "Out.Result" properties as read-only.

RESULT

app.PassFail.Rate.Result

RESULT

app.PassFail.Tests.Result

PREFERENCES

app.Preferences

This set of variables controls user preferences for the instrument setup and operation.

AudibleFeedback	Bool
EnhancedPrecisionMode	Bool
HorOffsetControl	Enum
Language	Enum
OffsetControl	Enum
Performance	Enum

AudibleFeedback

Bool

Description

Sets/Queries whether audible feedback is enabled, to sound when a control is touched.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Turn on the audible feedback function. app.Preferences.AudibleFeedback = True

EnhancedPrecisionMode

Bool

Description

EnhancedPrecisionMode

HorOffsetControl Enum

Description

HorOffsetControl.

Values

Div	
Time	

Language Enum

Description

Language

Values

ChineseSimplified	
English	
French	
German	
Italian	
Japanese	
Korean	

OffsetControl Enum

Description

Sets/Queries whether Vertical Offset constant in Volts or Divisions when the vertical scale control is changed.

Div	
Volts	

Performance Enum

Description

Sets/Queries the variable value that control the Optimization of the instrument in terms of analysis or display.

When set to Analysis the display is given low priority and will update less frequently. Use this mode where analysis performance is much more important than display rate.

Values

Analysis	
AnalysisMid	
Default	
Display	
DisplayMid	

EMAIL

app.Preferences.EMail

This set of variables controls user preferences for the instrument e-mail system.

E-Mail may be sent when the hardcopy button is pressed when the hardcopy system is appropriately configured. Two standards are supported, SMTP (Simple Mail Transport Protocol), and MAPI (Messaging Application Programming Interface).

DefaultRecipient	String
Mode	Enum
OriginatorAddress	String
SendTestMail	Action
SMTPServer	String

Example

- ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO")
- ' Configure the originator and recipient addresses, replace these with
- ' appropriate values for your corporate network.
- app.Preferences.Email.DefaultRecipient = "recipientAddress@do

DefaultRecipient

String

Range Any number of characters

Description

Sets/Queries the default recipient of e-mail transmissions.

Mode Enum

Description

Sets/Queries the transmission mode for e-mail.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set e-Mail mode to MAPI.
app.Preferences.EMail.Mode = "MAPI"
```

Values

MAPI	Messaging Application Programming Interface (Uses Outlook Express by default)
SMTP	Simple Mail Transfer Protocol, requires an SMTP server

Originator Address String

Range Any number of characters

Description

Sets/Queries the originator address for e-mail. This may be any address, and will be used when the recipient replies to a mail, note that the instrument doesn't necessarily have to have it's own E-Mail account in order to use this.

SendTestMail Action

Description

Sends a message by e-mail to test the system.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Send an e-Mail message to test the system.
app.Preferences.EMail.SendTestMail
```

SMTPServer String

Range Any number of characters

Description

Sets/Queries the name of the SMTP Server for e-mail. Ask your system administrator if you are unsure of what value to set this to.

RECALLSETUPLOCK

app.RecallSetupLock

SAVERECALL app. Save Recall

Controls for the Save/Recall subsystem. Includes nodes for saving and recalling both Waveforms and Panels (Setups).

ShowLSIBExport	Action

ShowLSIBExport Action

ShowSaveTable Action

SETUP app.SaveRecall.Setup

Controls for Saving and Recalling instrument setups.

DoRecallDefaultNvlPanel	Action
DoRecallDefaultPanel	Action
DoRecallPanel	Action
DoSavePanel	Action
InternalName1	String
InternalName2	String
InternalName3	String
InternalName4	String
InternalName5	String
InternalName6	String
PanelDir	FileName
PanelFilename	FileName
RecallInternal1	Action
RecallInternal2	Action
RecallInternal3	Action
RecallInternal4	Action
RecallInternal5	Action
RecallInternal6	Action
SaveInternal1	Action
SaveInternal2	Action
SaveInternal3	Action
SaveInternal4	Action
SaveInternal5	Action
SaveInternal6	Action

Example

- ' Visual Basic Script
 Set app = CreateObject("LeCroy.XStreamDSO")
- ' Reset to default setup app.SaveRecall.Setup.DoRecallDefaultPanel
- ' Store the current setup into the first of the 6 setup stores. app.SaveRecall.Setup.InternalName1 = "My Setup1" \square

DoRecallDefaultNvlPanel

Action

Description

Recalls the factory set NVL (preference) panel settings. These are controls which are not affected when the default panel is recalled, and includes items such as the color preferences, remote control

preferences, etc. Use with care!, especially when invoking via the VBS? Remote command via GPIB or TCP/IP, which could result in the controller being disconnected when the default port is selected.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Recall the factory default nvl panel settings.
app.SaveRecall.Setup.DoRecallDefaultNvlPanel
```

DoRecallDefaultPanel Action

Description

Recalls the factory set panel settings.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Recall the factory default panel settings.
app.SaveRecall.Setup.DoRecallDefaultPanel
```

DoRecallPanel Action

Description

Recall the panel file named in the PanelFilename control.

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Create the filename for the next panel setup to be recalled.
app.SaveRecall.Setup.PanelFilename = "Setup89"

'Recall the panel setup from the named file.
app.SaveRecall.Setup.DoRecallPanel
```

DoSavePanel Action

Description

Saves the current panel settings to the previously specified file. If the filename already exists, the file will be over-written without a prompt.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Create the filename for the next panel setup save.
app.SaveRecall.Setup.PanelFilename = "TestSave"
' Save the panel setup to the named file.
app.SaveRecall.Setup.DoSavePanel
```

InternalName1 String

Range Any number of characters

Description

Sets/Queries the name of internal panel setup memory 1.

InternalName2 String Any number of characters Range Description Please see InternalName1. InternalName3 String Any number of characters Range Description Please see InternalName1. InternalName4 String Any number of characters Range Description Please see InternalName1. InternalName5 String Any number of characters Range Description Please see InternalName1. InternalName6 String Any number of characters Range Description Please see InternalName1. **PanelDir FileName** Any number of characters Range Description Directory in which setups are stored/recalled. **PanelFilename FileName** Any number of characters Range

Description

Sets/Queries the current filename for saving a panel setup. Note that a '.lss' extension is automatically appended if not supplied.

RecallInternal1 Action Description Recall the settings which are stored in internal panel memory 1. **Example** ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO") ' Recall the settings from internal panel memory 1. app.SaveRecall.Setup.RecallInternal1 RecallInternal2 Action Description Please see RecallInternal1. RecallInternal3 Action Description Please see RecallInternal1. RecallInternal4 Action Description Please see RecallInternal1. RecallInternal5 Action Description Please see RecallInternal1. RecallInternal6 Action Description Please see RecallInternal1. SaveInternal1 Action Saves the current instrument settings into internal panel memory 1. Example ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO") ' Save the current settings into internal panel memory 1. app.SaveRecall.Setup.SaveInternal1 SaveInternal2 Action Description Please see SaveInternal1. SaveInternal3 Action Description Please see SaveInternal1.

SaveInte	rnal4		Action
Descrip	ption		
	ase see SaveInternal1.		
SaveInte	rnal5		Action
Descrip Plea	ption ase see SaveInternal1.		
SaveInte	rnal6		Action
Descrip Plea	ption ase see SaveInternal1.		
TABLE	E	app.Sav	eRecall.Table
	Delimiter	Enum	
	DoSave	Action	
	SaveSource	Enum	
	TableDir	FileName	
	TableFormat	Enum	
	TableTitle	String	
Dolimitor			Enum
Delimiter Values			Enum
			Enum
	S		Enum
	S Comma		Enum
	Comma Semicolon		Enum
	Comma Semicolon Space		Enum Action
Values	Comma Semicolon Space Tab		
Values DoSave	Comma Semicolon Space Tab		Action
Values DoSave SaveSou	Comma Semicolon Space Tab		Action
Values DoSave SaveSou	Comma Semicolon Space Tab IFCE S AllDisplayed		Action
Values DoSave SaveSou Values	Comma Semicolon Space Tab IICE S AllDisplayed		Action Enum
Values DoSave SaveSou Values TableDir	Comma Semicolon Space Tab Irce S AllDisplayed Any number of characters		Action Enum
Values DoSave SaveSou Values TableDir Range	Comma Semicolon Space Tab Irce S AllDisplayed Any number of characters		Action Enum FileName
Values DoSave SaveSou Values TableDir Range TableFor	Comma Semicolon Space Tab Irce S AllDisplayed Any number of characters		Action Enum FileName

TableTitle String

Range Any number of characters

UTILITIES app. Save Recall. Utilities

Controls used to manage files and folders, including the ability to create and delete folders, and the ability to delete files.

CreateDir	Action
DeleteAll	Action
DeleteFile	Action
Directory	FileName

CreateDir Action

Description

Creates the directory specified in the Directory control.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Create a named directory
app.SaveRecall.Utilities.Directory = "C:\MyDir"
app.SaveRecall.Utilities.CreateDir
```

DeleteAll Action

Description

Deletes all files in the directory specified by the Directory control without a cautionary prompt. Use with care! Files cannot be recovered if deleted accidentally.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Delete all files without showing a yes/no prompt.
app.SaveRecall.Utilities.Directory = "C:\MyDir"
app.SaveRecall.Utilities.DeleteAll
```

DeleteFile Action

Description

Deletes the file named by the Filename control

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Delete the named file
app.SaveRecall.Utilities.Filename = "C:\MyDir\MyFile.txt"
app.SaveRecall.Utilities.DeleteFile
```

Directory FileName

Range Any number of characters

Description

Defines the directory which will be used for the operations in this automation node.

WAVEFORM

app.SaveRecall.Waveform

Contains controls used for saving and recalling waveforms.

Delimiter	Enum
DoRecall	Action
DoSave	Action
RecallDestination	Enum
RecallFrom	Enum
RecallSource	Enum
SaveDestination	Enum
SaveSource	Enum
SaveTo	Enum
TraceTitle	String
WaveFormat	Enum
WaveformDir	FileName

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Save C1 into M1
app.SaveRecall.Waveform.SaveTo = "Memory"
app.SaveRecall.Waveform.SaveSource = "C1"
app.SaveRecall.Waveform.SaveDestination = "M1"
app.SaveRecall.Waveform.DoSave
```

Delimiter Enum

Description

Sets/Queries the delimiter to use when saving data in ASCII text mode.

Values

Comma	
Semicolon	
Space	
Tab	

DoRecall Action

Description

Recall waveform data into a trace memory. Source may be either an internal memory (M1..M4), or a file on a mass-storage device, depending on the state of the 'RecallFrom' control.

		Command and Query Reference Manual - Control Reference	
DoSave			Action
		to an internal memory, or file on a mass-storage device, using the pre-specified	
RecallDes	stination		Enum
Descrip	tion		
		nation for waveform recall. When the DoRecall action is executed the waveform this destination trace.	
Values			
	M1		
	M2		
	M3		
	M4		
RecallFro	m		Enum
RecallFro Descrip			Enum
Descrip	tion	of source for waveform recall.	Enum
Descrip	tion /Queries the type o	of source for waveform recall.	Enum
Descrip Sets.	tion /Queries the type o	of source for waveform recall. Recall from file on a mass-storage device	Enum
Descrip Sets.	tion /Queries the type o		Enum
Descrip Sets Values	tion /Queries the type o File Memory	Recall from file on a mass-storage device	Enum
Description Sets. Values RecallSou	tion /Queries the type of File Memory	Recall from file on a mass-storage device	
Descript Sets Values RecallSou Descript Sets	File Memory Jrce tion /Queries the source	Recall from file on a mass-storage device Recall from one of the internal memories (M1M4) e for recalling waveform data. Used only when recalling from an internal	
Descript Sets Values RecallSou Descript Sets	tion /Queries the type of File Memory Jrce tion	Recall from file on a mass-storage device Recall from one of the internal memories (M1M4) e for recalling waveform data. Used only when recalling from an internal	
Descript Sets Values RecallSou Descript Sets	File Memory LICE tion /Queries the source nory with RecallSou	Recall from file on a mass-storage device Recall from one of the internal memories (M1M4) e for recalling waveform data. Used only when recalling from an internal	
Description Sets. Values RecallSouth Description Sets. mem	File Memory LICE tion /Queries the source nory with RecallSou	Recall from file on a mass-storage device Recall from one of the internal memories (M1M4) e for recalling waveform data. Used only when recalling from an internal	
Description Sets. Values RecallSouth Description Sets. mem	File Memory LICE tion /Queries the source nory with RecallSou	Recall from file on a mass-storage device Recall from one of the internal memories (M1M4) e for recalling waveform data. Used only when recalling from an internal	
Description Sets. Values RecallSouth Description Sets. mem	File Memory Jrce tion /Queries the source nory with RecallSou	Recall from file on a mass-storage device Recall from one of the internal memories (M1M4) e for recalling waveform data. Used only when recalling from an internal	

SaveDestination Enum

Description

Sets/Queries the destination to which waveform data will be saved. Used only when the SaveTo = "Memory".

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Setup to store trace C2 into M4 and perform the save operation app.SaveRecall.Waveform.SaveTo = "Memory" app.SaveRecall.Waveform.SaveSource = "C2" app.SaveRecall.Waveform.SaveDestination = "M4" app.SaveRecall.Waveform.DoSave
```

M1	
M2	
M3	
M4	

SaveSource Enum

Description

Sets/Queries the source from which waveform data will be saved.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Set the destination to memory for waveform save.
app.SaveRecall.Waveform.SaveTo = "Memory"
' Set the source to C2, for saving a waveform.
app.SaveRecall.Waveform.SaveSource = "C2"
' Set the destination to memory M4, for saving a waveform.
app.SaveRecall.Waveform.SaveDestination = "M4"
' Save waveform data as previously specified.
app.SaveRecall.Waveform.DoSave
```

AllDisplayed	
BadBits	
BadBits2	
Bits	
Bits2	
C1	
C2	
C3	
C4	
Digital1	
Digital2	
Digital3	
Digital4	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye	
Eye2	
F1	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
FLXEye	
Harm	
1	

M1	
M2	
M3	
M4	
Mod	
PointA	
PointB	
PointC	
PointD	
PointF	
PointH	
PRBS	
Pwr	
R	
ScanHisto	
ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	
V	
Z1	
Z2	
Z3	
Z4	
Z5	
Z6	
Z7	
Z8	

SaveTo Enum

Description

Sets/Queries type of destination for waveform save.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Set the destination to Memory for waveform save.
app.SaveRecall.Waveform.SaveTo = "Memory"

File	Save into file on a mass-storage device
Memory	Save into an internal memory (M1M4)

TraceTitle String

Range Any number of characters

Description

Sets/Queries the title (prefix) to use when naming saved traces. This prefix will have the family (sequence) number appended to it when forming the filename.

WaveFormat Enum

Description

Sets/Queries the format to use when saving waveform data into a file. 'Binary' is the most efficient, storing one or two bytes per data sample, depending upon the number of significant bits. When in ASCII mode, the Subformat and Delimiter controls define the data format.

Values

ASCII	Plain ASCII files with choice of various delimiters
Audio	
Binary	LeCroy's standard binary waveform format
Excel	
MathCad	
MATLAB	

WaveformDir FileName

Range Any number of characters

Description

Sets/Queries the directory for storing waveform files.

SDA app.SDA

Controls used for SDA (Serial Data Analysis) models only.

AnyHasClientChanged	Action
BERParamsOn	Bool
BERPow10	Integer
CDRon	Bool
ClearSweeps	Action
ClkJitterDisplay	Enum
ClockModeOn	Bool
CompensateForMissingEdges	Bool
CompensateNoise	Bool
CustomPLL2PoleDamping	Double
CustomPLL2PoleDamping2	Double
CustomPLL2PoleNaturalFreq	Double
CustomPLL2PoleNaturalFreq2	Double
CustomPLLFilterNumPoles	Integer
CustomPLLFilterPoleFreq	Double
CustomPLLFilterZeroFreq	Double
CustomPLLTransportDelay	Double

DataSource	Enum
DataSource2	Enum
DataSource3	Enum
Deskew	Double
DoRecallDefaultPanel	Action
DSTB	Enum
DSTBN	Enum
DSTBP	Enum
ErrorMapOn	Bool
ExecutiveListChanged	Action
EyeGate	Enum
EyeMode	Enum
EyeThresholdFind	Action
EyeThresholdType	Enum
FilterType	Enum
FindFrequency	Action
FindNoise	Action
FindPattern	Action
FrameMode	Enum
FrequencyMultiplier	Integer
FSBWrite	Enum
InstrumentNoise	Double
IntervalsEdgeEdge	Integer
IntervalType	Enum
JitterClockWizard	Action
JitterMeasurement	Enum
MaskTestGrid	Action
MaskTypeEye2	Enum
PatternLength	Integer
PermitGTHalfUI	Bool
PLLCutOff	Integer
PIIFBDIMMEqnImage	Image
PLLFrequency	Double
PLLOn	Bool
PLLprompt	String
PLLType	Enum
ReferenceFrequency	Double
RefPercentLevel	Double
RefSource	Enum
RefThresholdFind	Action
RefThresholdType	Enum
RescaleSpectrum	Action
RunThenStop	Action
SDAJitterWizard	Action
SDAMode	Enum
ShowBathtub	Bool
- CHO TO GRANDO	5001

ShowDDjHisto	Bool
ShowEyeDiagram	Bool
ShowFailLocation	Bool
ShowJitterHisto	Bool
ShowJitterTrack	Bool
ShowMask	Bool
ShowPjSpectrum	Bool
ShowQScaleFit	Bool
ShowSnCycle	Bool
ShowTopDialog	Action
SignalFrequency	Double
SignalMode	Enum
SignalType	Enum
SummaryGrid	Action
TIEPercentLevel	Double
TIESignalType	Enum
TIESlope	Enum
TransitionDensity	Double
UpdateVerticalNoise	Action
UseAllEdges	Bool

AnyHasClientChanged	Action
BERParamsOn	Bool
Description Sets/Queries whether the bit error rate parameters are shown.	

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Set the BER parameters on. app.SDA.BERParamsOn = True

BERPow10 Integer

Range From -16 to -1 step 1

CDRon Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

Enum

ClkJitterDisplay

Values Bathtub FilteredJitter JitterHistogram nCyclevsN ClockModeOn Bool CompensateForMissingEdges Bool CompensateNoise Bool Double CustomPLL2PoleDamping From 0.5 to 2 step 0.001 Range CustomPLL2PoleDamping2 Double Range From 0.5 to 2 step 0.001 Double CustomPLL2PoleNaturalFreq From 208333 to 3e+008 step 1000 Range CustomPLL2PoleNaturalFreq2 Double From 208333 to 3e+008 step 1000 Range **CustomPLLFilterNumPoles** Integer From 1 to 2 step 1 Range Double CustomPLLFilterPoleFreq From 100000 to 3e+008 step 1000 Range CustomPLLFilterZeroFreq Double From 100000 to 6e+008 step 100000 Range CustomPLLTransportDelay Double From 0 to 1 step 1e-015 Range

DataSource Enum

Description

Sets/Queries the data source trace for SDA.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the instrument into SDA mode.
app.SDA.SDAMode = "MaskTest"
' Set the data source as trace C3.
app.SDA.DataSource = "C3"
```

C1	
C2	
C3	
C4	
F1	
F2	
F3	
F4	
M1	
M2	
M3	
M4	
Z1	
Z2	
Z3	
Z4	
Z5	
Z6	
Z7	
Z8	

	Automation Co	mmand and Query Reference Manual - Control Reference	
DataSour	ce2		Enum
Values			
values			
	C1 C2		
	C3		
	C4		
	F1		
	F2		
	F3		
	F4		
	M1		
	M2		
	M3		
	M4		
	Z1		
	Z2		
	Z3		
	Z4		
DataSour Values			Enum
	C1		
	C2		
	C3		
	C4		
	F1		
	F2		
	F3		
	F4		
	M1		
	M2		
	M3		
	M4		
	Z1		
	Z2		
	Z3		
	Z4		
Deskew			Double
Range	From -1e-008 to 1e	e-008 step 1e-012	
DoRecall	DefaultPanel		Action

DSTB Enum

Values

C1	
C2	
C3	
C4	
F1	
F2	
F3	
F4	
M1	
M2	
M3	
M4	
Z1	
Z2	
Z3	
Z4	

DSTBN Enum

•	
C1	
C2	
C3	
C4	
F1	
F2	
F3	
F4	
M1	
M2	
M3	
M4	
Z1	
Z2	
Z3	
Z4	

DSTBP Enum

Values

C1	
C2	
C3	
C4	
F1	
F2	
F3	
F4	
M1	
M2	
M3	
M4	
Z1	
Z 2	
Z3	
Z4	

Error Map On Book

Description

Sets/Queries whether the error map is on.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the error map on.
app.SDA.ErrorMapOn = True
```

ExecutiveListChanged

Action

EyeGate Enum

Values

C1	
C2	
C3	
C4	
F1	
F2	
F3	
F4	
M1	
M2	
M3	
M4	
Z1	
Z 2	
Z3	
Z4	

EyeMode Enum

Description

Sets/Queries the type of eye diagram.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the eye mode as traditional.
app.SDA.EyeMode = "Traditional"
```

Values

FSB	
Gated	
Sequential	
Traditional	
Transition	

EyeThresholdFind Action

EyeThresholdType Enum

Absolute	
Percent	

Values PCleG2Hbi PCleG2Hb	FilterTyp	е	Enum
PCIeG2Hni PCIeG2Hni UserSpecified FindFrequency Description Instruct the instrument to find the frequency of the signal. Example ' Visual Basic Script Set app = CreateObject ("LeCroy.XStreamDSO") ' Find the frequency.	Values	5	
PCIGG2Hio UserSpecified			
UserSpecified			
FindFrequency Description Instruct the instrument to find the frequency of the signal. Example ' Visual Basic Script Set app = CreateObject ("LeCroy.XStreamDSO") ' Find the frequency. app.SDA.FindFrequency FindPattern Action FrameMode Values Header Orf Size SizeandHeader SONET WithOverhead WithOverheadAndCount			
Description Instruct the instrument to find the frequency of the signal. Example ' Visual Basic Script Set app = Create@bject("LeCroy.XStreamDSO") ' Find the frequency app.SDA.FindFrequency FindNoise Action FrameMode FrameMode FrameMode FindPattern Values Header Off Size SizeandHeader SONET WithOverhead WithOverhead WithOverhead WithOverhead From 1 to 1 step 1 FSBWrite Values Data1 Data2 Data3 InstrumentNoise Range From 0 to 0.05 step 1e-005 Integer	FindFred		Action
Instruct the instrument to find the frequency of the signal. Example		•	, ionen
Page	_		
' Visual Basic Script Set app = CreateObject ("LeCroy.XStreamDSO") ' Find the frequency app.SDA.FindFrequency FindNoise			
Set app = CreateObject ("LeCroy.XStreamDSO") Find the frequency app.SDA.FindFrequency FindNoise			
FindNoise Action FindPattern Action FrameMode Enum Values Header Off Size SizeandHeader SONET WithOverhead WithOverhead WithOverhead From 1 to 1 step 1 FSBWrite Enum Values Data1 Data2 Data3 InstrumentNoise Range From 0 to 0.05 step 1e-005 Integer Integer Integer			
FindPattern			
Header	FindNois	е	Action
Header	FindPatte	ern	Action
Header	FrameMo	ode	Enum
Off	Values	5	
Size SizeandHeader SONET WithOverhead Wit		Header	
SizeandHeader SONET WithOverhead WithOverhead WithOverheadAndCount Integer Range From 1 to 1 step 1 Enum Values Data1 Data2 Data3 InstrumentNoise Range From 0 to 0.05 step 1e-005 Integer		Off	
SONET		Size	
WithOverhead WithOverheadAndCount		SizeandHeader	
WithOverheadAndCount		SONET	
Integer Range From 1 to 1 step 1 FSBWrite Enum		WithOverhead	
Range From 1 to 1 step 1 Enum Values Data1		WithOverheadAndCount	
Values	Frequenc	cyMultiplier	Integer
Values Data1 Data2 Data3 Data3 InstrumentNoise Double Range From 0 to 0.05 step 1e-005 IntervalsEdgeEdge Integer	Range	From 1 to 1 step 1	
Data1	FSBWrite	}	Enum
Data2 Data3 InstrumentNoise Range From 0 to 0.05 step 1e-005 IntervalsEdgeEdge Integer	Values	5	
InstrumentNoise Range From 0 to 0.05 step 1e-005 IntervalsEdgeEdge Integer		Data1	
InstrumentNoise Range From 0 to 0.05 step 1e-005 IntervalsEdgeEdge Integer		Data2	
Range From 0 to 0.05 step 1e-005 IntervalsEdgeEdge Integer		Data3	
IntervalsEdgeEdge Integer	Instrume	ntNoise	Double
	Range	From 0 to 0.05 step 1e-005	
	Intervals	EdgeEdge	Integer

IntervalT	уре	Enum
Values	S	
	EDGEREF	
JitterClo	ckWizard	Action
JitterMea	asurement	Enum
Value	s	
	Advanced	
	Basic	
	Djbreakdown	
	Off	
MaskTes	stGrid	Action
MaskTyp	peEye2	Enum
Values	s	
	Absolute	
	Normalized	
PatternL	ength	Integer
Range	From 1 to 2147483647 step 1	
PermitG	THalfUI	Bool
PLLCutO	Off	Integer
Range	From 10 to 1000000 step 1	
PIIFBDIN	/IMEqnImage	Image
PLLFreq	uency	Double
Range	From 1250 to 1.25e+008 step 1	
PLLOn		Bool
Descri p Set	ption s/Queries use of a PLL to track the clock frequency.	
	ole Visual Basic Script app = CreateObject("LeCroy.XStreamDSO")	
	Set the PLL off. o.SDA.PLLOn = False	

PLLprom	ot	String
Range	Any number of characters	
PLLType		Enum
Values		
	Custom	
	DVI	
	FBDIMM	
	GOLDEN	
Reference	eFrequency	Double
Range	From 90000 to 4e+010 step 1	
RefPerce	ntLevel	Double
Range	From 0 to 100 step 1	
RefSourc	e	Enum
Values		
	C1	
	C2	
	C3	
	C4	
	F1	
	F2	
	F3	
	F4	
	M1	
	M2	
	M3	
	M4	
	Z1	
	Z2	
	Z3	
	Z4	
	Z5 Z5	
	Z5	

RefThres	holdType		Enum
Values	i		
	Absolute		
	Percent		
RescaleS	pectrum		Action
RunThen	Stop		Action
SDAJitte	Wizard		Action
SDAMode	 •		Enum
Descrip	tion		
Valu		operation of the instrument. Jitter,BER,Clock,Summary for SDA+ASDA for SDM	
Exampl	e		
	isual Basic Scrip		
Set	app = CreateObje	ct("LeCroy.XStreamDSO")	
	et the instrument .SDA.SDAMode = "M	into Mask Test mode. askTest"	
Values			
	MaskTest Scope		
ShowBat			Bool
SHOWDAL			
ShowDDj	Histo		Bool
ShowEye	Diagram		Bool
ShowFail	Location		Bool
Descrip Sets		k failures are to be shown by markers.	
	isual Basic Scrip	t ct("LeCroy.XStreamDSO")	
	how locations of		
	.SDA.ShowFailLoca		
ShowJitte	erHisto		Bool
ShowJitte	erTrack		Bool
ShowMas	sk		Bool

ShowPjSpectrum	Вооі
ShowQScaleFit	Bool
ShowSnCycle	Bool
ShowTopDialog	Action
SignalFrequency	Double
Range From 90000 to 4e+010 step 1	
Description Sets/Queries the signal frequencies.	
<pre>Example ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO")</pre>	
' Set the signal frequency to 15 MHz. app.SDA.SignalFrequency = 15e6	
SignalMode	Enum

Description

Values for this control depend upon SDA standard set by SignalType control.

Receiver	
TransAbs	
TransNrm	

SignalType Enum

Description

Sets/Queries the signal type for SDA.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the instrument into SDA mode.
app.SDA.SDAMode = "MaskTest"
' Set signal type as STM16.
app.SDA.SignalType = "STM16"
```

Values

1000BaseCX	
1000BaseLX	
1000BaseSX	
Custom	
DVI	
FC1063	
FC133	
FC266	
FC531	
FlexRay10.0Mbitss	
FlexRay2.5Mbitss	
FlexRay5.0Mbitss	
FSB533Mhz	
FSB667Mhz	
FSB800Mhz	
HDMI1.3148.5MHz	
HDMI1.325MHz	
HDMI1.327MHz	
HDMI1.374.25MHz	
IEEE1394b	
OC1	
OC12	
OC3	
RapidIOLPSerial	
RapidIOParallel	
STM1Optical	
STM4Optical	
STS1Eye	
STS3	
USB2.0	

SummaryGrid Action

TIEPercentLevel		Double
Range	From 0 to 100 step 1	
TIESignal	- уре	Enum
Values		
	Clock	
	Data	
TIESlope		Enum
Values		
	Both	
	Neg	
	Pos	
Transition	Density	Double
Range	From 0.1 to 1 step 0.01	
UpdateVe	ticalNoise	Action
UseAllEdg	es	Bool

app.SDA.BadBits **BADBITS**

AxisXRotation	Integer
AxisYRotation	Integer
BitsInLocator	Integer
C1ReceiverStandard	Enum
C2ReceiverStandard	Enum
C3ReceiverStandard	Enum
C4ReceiverStandard	Enum
ClearSweeps	Action
ClockTIESlope	Enum
EyeMode	Enum
EyeThresholdType	Enum
FailCursorsOn	Bool
FailedList	Enum
FailedListEye2	Enum
FailedSymbolsFilter	Enum
FailedSymbolsFilterEye2	Enum
LabelsPosition	String
LabelsText	String
MaskFailX	Double
MaskFailXEye2	Double

MaskFailY	Double
MaskFailYEye2	Double
MaxFailures	Integer
MeasurementMode	Enum
MonochromeEye	Enum
PercentLevel	Integer
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
Saturation	Integer
ShowFailLocation	Bool
ShowLastTrace	Bool
SignalFrequency	Double
SignalMode	Enum
SliceWidth	Integer
Stop	Bool
TrackMaskFail	Action
UseGrid	String
VerAutoFit	Bool
ViewLabels	Bool
XMargin	Integer
YMargin	Integer

AxisXRotation Integer

Range From -90 to 90 step 1

Description

Using SDA.BadBits.Persisted, please refer to the corresponding variable in Display.

AxisYRotation Integer

Range From -90 to 90 step 1

Description

Using SDA.BadBits.Persisted, please refer to the corresponding variable in Display.

BitsInLocator Integer

Range From 1 to 101 step 2

Description

Number of bits to display in the Mask Test bottom grid where the bit that failed the mask shows in the center of the grid. For example, BitsInLocator = 5 means that 2 bits before and 2 bits after the failing bit are going to display in the bottom grid.

C1ReceiverStandard	Enum
--------------------	------

Description

Read only. Indicates what reference receiver filter the optical to electrical converter uses on the SDA signal.

Values

DISABLED	
FC1063	
FC2125	
L1000BASE	
OC12	
OC3	
OC48	
OTHER	

C2ReceiverStandard Enum

Description

Read only. Indicates what reference receiver filter the optical to electrical converter uses on the SDA signal.

Values

DISABLED	
FC1063	
FC2125	
L1000BASE	
OC12	
OC3	
OC48	
OTHER	

C3ReceiverStandard Enum

Description

Read only. Indicates what reference receiver filter the optical to electrical converter uses on the SDA signal.

DISABLED	
FC1063	
FC2125	
L1000BASE	
OC12	
OC3	
OC48	
OTHER	

Automation Command and Query Reference Manual - Control Reference			
C4Receiv	/erStandard		Enum
Descrip	otion		
-	d only. Indicates what	reference receiver filter the optical to electrical converter uses on the SDA	
Values	;		
	DISABLED		
	FC1063		
	FC2125		
	L1000BASE		
	OC12		
	OC3		
	OC48		
	OTHER		
ClearSwe	eens		Action
Descrip			
Usir	ng SDA.BadBits.Persis	sted, please refer to the corresponding variable in Acquisition.Cx	
ClockTIE	Slope		Enum
Descrip	otion		
-		eye diagram alignment.	
Values			
	Both		
	Negative		
	Positive		
EyeMode			Enum
_			
Descrip			
Usir	ng SDA.BadBits, refer	to the corresponding variable in SDA.	
Values	i		
	FSB		
	Gated		
	Sequential		
	Traditional		
	Transition		
	L		

EyeThres	holdType	Enum
Descrip	otion	
Thre	eshold type for Eye Diagram TIE level. Change the Eye Diagram TIE settings to match the	
	ected eye crossings. For example, SDA default for eye crossing at 50%. The user can set it to	
Eye	ThresholdType = Percent and PercentLevel=32.	
Values		
	Absolute	
	Percent	
FailCurso	orsOn	Bool
Descrip	otion	
_	n on/off round cursors around points in the eye diagram that penetrate the mask.	
FailedLis		Enum
raileuLis	· ·	Liiuiii
Descrip	tion	
Rea	d the indices of the bits the failed the mask test.	
Values		
FailedLis	tEye2	Enum
Values		
FailedSyı	mbolsFilter	Enum
Descrip	otion	
Set	what failed indices to get in the FailedList. Values: All, NearXY. For NearXY, see MaskFailX and kFailY.	
Values		
FailedSyı	mbolsFilterEye2	Enum
Values		
LabelsPo	sition	String
Range	Any number of characters	
Descrip Usir	otion ng SDA.BadBits.Persisted, please refer to the corresponding variable in Acquisition.Cx	
LabelsTe	xt	String
Range	Any number of characters	
Descrip Usir	otion ng SDA.BadBits.Persisted, please refer to the corresponding variable in Acquisition.Cx	

MaskFailX	(Double
Range	From 0 to 1 step 0.01	
Descript	tion	
clicks	ws the relative horizontal position of the selected mask failure cursors. For example, the user s on a mask failure cursors in the middle of the display. MaskFailX shows the selected horizontal ion that would be 0.5.	
MaskFailX	(Eye2	Double
Range	From 0 to 1 step 0.01	
MaskFailY	· · · · · · · · · · · · · · · · · · ·	Double
Range	From 0 to 1 step 0.01	
Descript	tion	
on a	ws the relative vertical position of the selected mask failure cursors. For example, the user clicks mask failure cursors in the middle of the display. MaskFailY shows the selected vertical position would be 0.5.	
MaskFailY	/Eye2	Double
Range	From 0 to 1 step 0.01	
MaxFailur	es	Integer
Range	From 1 to 10000 step 1	
Descript Set t	tion he number of failed bits to display in FailedList.	
Measurem	nentMode	Enum
Descript	tion	
Displ	lay a set of parameters measuring various properties of the eye diagram.	
Values		
	Amplitude	
	Eye	
	MaskTest	
	Off	
	Timing	
Monochro	omeEye	Enum
Values		
	Colorgraded	
	Monochrome	
PercentLe	evel	Integer
Range	From 0 to 100 step 1	

Persist3D	Quality		Enum
Descrip Usin		ed, please refer to the corresponding variable in Acquisition.Cx	
Values			
	Shaded		
	Solid		
	WireFrame		
Persisted			Bool
Descrip Usin		ed, please refer to the corresponding variable in Acquisition.Cx	
Persisten	ce3d		Bool
Descrip Usin		ed, please refer to the corresponding variable in Acquisition.Cx	
Persisten	ceMonoChrome		Bool
Descrip Usin		ed, please refer to the corresponding variable in Acquisition.Cx	
Persisten	ceSaturation		Integer
Range	From 0 to 100 step 1		
Descrip Usin		ed, please refer to the corresponding variable in Acquisition.Cx	
Persisten	ceTime		Enum
Descrip Usin		ed, please refer to the corresponding variable in Acquisition.Cx	
Values			
	0.5s		
	10s		
	1s		
	20s		
	2s		
	5s		
	Infinite		
Saturation	n		Integer
Range	From 0 to 100 step 1		
ShowFail	Location		Bool
Descrip Usin		o the corresponding variable in SDA.	
USITI	g CD/ LDaaDits, Tolel to	the conceptioning variable in ODA.	

ShowLas	stTrace	Bool
Descri	otion	
Usi	ng SDA.BadBits.Persisted, please refer to the corresponding variable in Acquisition.Cx	
SignalFr	equency	Double
Range	From 90000 to 4e+010 step 1	
Descri Usi	otion ng SDA.BadBits, refer to the corresponding variable in SDA.	
SignalMo	ode	Enum
Values		
	Receiver	
	TransAbs	
	TransNrm	
SliceWid	th	Integer
Range	From 0 to 100 step 1	
	otion Diagram measurement aid. Applies a vertical slice around the middle of the eye diagram for rowing measurement areas.	
Stop		Bool
Descri	otion	
Sto	p acquisition when the signal penetrates the mask.	
TrackMa	skFail	Action
Descrip	otion	
Usi	ng SDA.BadBits, refer to the corresponding variable in SDA.	
UseGrid		String
Range	Any number of characters	
Descri		
Usi	ng SDA.BadBits.Persisted, please refer to the corresponding variable in Acquisition.Cx	
VerAutoF	Fit Control of the Co	Bool
Descri p Usi	otion ng SDA.BadBits, refer to the corresponding variable in SDA.	
ViewLab	els	Bool
Descri	ation	
-	ng SDA.BadBits.Persisted, please refer to the corresponding variable in Acquisition.Cx	

XMargin Integer

Range From 0 to 100 step 1

Description

Inflate the mask horizontally. Values: 0-100 in percent. 0 Means original mask; 100% means the mask stretches all the way over the horizontal span.

YMargin Integer

Range From 0 to 100 step 1

Description

Inflate the mask vertically. Values: 0-100 in percent. 0 Means original mask; 100% means the mask stretches all the way over the vertical span.

RESULT

app.SDA.BadBits.Out.Result

BITS app.SDA.Bits

AxisXRotation	Integer
AxisYRotation	Integer
ClearSweeps	Action
LabelsPosition	String
LabelsText	String
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ShowLastTrace	Bool
UseGrid	String
View	Bool
ViewLabels	Bool

AxisXRotation Integer

Range From -90 to 90 step 1

Description

Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx

AI-VD-(-tl	Intono
AxisYRotation	Integer
Range From -90 to 90 step 1	
Description Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx	
ClearSweeps	Action
Description Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx	
LabelsPosition	String
Range Any number of characters	
Description Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx	
LabelsText	String
Range Any number of characters	
Description Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx	
Persist3DQuality	Enum
Description Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx	
Values	
Shaded	
Solid	
WireFrame	
Persisted	Bool
Description Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx	
Persistence3d	Bool
Description Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx	
PersistenceMonoChrome	Bool
Description Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx	
PersistenceSaturation	Integer
Range From 0 to 100 step 1	
Description Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx	

PersistenceTime Enum

Description

Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

ShowLastTrace Bool

Description

Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx

UseGrid String

Range Any number of characters

Description

Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx

View Bool

Description

Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx

ViewLabels Book

Description

Using SDA.Bits.View, please refer to the corresponding variable in Acquisition.Cx

RESULT

app.SDA.Bits.Out.Result

Properties of the type xxxx.Out.Result.yyyy are those of the last completed acquisition. They are not affected if other cvars are changed after that acquisition was completed. This distinction between "Out.Result" properties and other cvars is most important when the trigger mode is Single or Stopped. You should treat "Out.Result" properties as read-only.

EYE app.SDA.Eye

AxisXRotation	Integer
AxisYRotation	Integer
ClearSweeps	Action
LabelsPosition	String
LabelsText	String

Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ShowLastTrace	Bool
UseGrid	String
View	Bool
ViewLabels	Bool

AxisXRotation Integer From -90 to 90 step 1 Range Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. **AxisYRotation** Integer From -90 to 90 step 1 Range Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. **ClearSweeps** Action Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. LabelsPosition String Any number of characters Range Description Using SDA. Eye, please refer to the corresponding variable in Acquisition. Cx. LabelsText String Any number of characters Range Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. Persist3DQuality **Enum** Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. **Values** Shaded

Solid WireFrame

Persisted Bool Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. Persistence3d Bool Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. **PersistenceMonoChrome** Bool Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. **PersistenceSaturation** Integer From 0 to 100 step 1 Range Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. Enum **PersistenceTime** Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. **Values** 0.5s 10s 1s 20s 2s 5s Infinite **ShowLastTrace** Bool Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. **UseGrid** String Any number of characters Range Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx. View Bool Description Using SDA.Eye, please refer to the corresponding variable in Acquisition.Cx.

ViewLabels Bool

Description

Using SDA. Eye, please refer to the corresponding variable in Acquisition. Cx.

RESULT

app.SDA.Eye.Out.Result

Properties of the type xxxx.Out.Result.yyyy are those of the last completed acquisition. They are not affected if other cvars are changed after that acquisition was completed. This distinction between "Out.Result" properties and other cvars is most important when the trigger mode is Single or Stopped. You should treat "Out.Result" properties as read-only.

FINDFREQREFERENCE

app.SDA.FindFreqReference

ClearSweeps	Action
FindFrequencyConfirm	Action
SignalType	Enum
View	Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

FindFrequencyConfirm

Action

SignalType

Enum

Values

Clock	
Data	

View Book

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SDA.FindFreqReference.Out.Result

FINDFREQSTREAM

app.SDA.FindFreqStream

ClearSweeps	Action
-------------	--------

FindFrequencyConfirm	Action
SignalType	Enum
View	Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

FindFrequencyConfirm Action

SignalType Enum

Values

Clock	
Data	

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SDA.FindFreqStream.Out.Result

FINDLEVELREFERENCE

app.SDA.FindLevelReference

ClearSweeps	Action
ThresholdFindConfirm	Action
View	Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

ThresholdFindConfirm Action

View Book

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SDA.FindLevelReference.Out.Result

FINDLEVELSTREAM

app.SDA.FindLevelStream

ClearSweeps	Action
ThresholdFindConfirm	Action
View	Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

ThresholdFindConfirm Action

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SDA.FindLevelStream.Out.Result

MASK2HITS

app.SDA.Mask2Hits

ClearSweeps	Action
View	Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SDA.Mask2Hits.Out.Result

MASK2OUT app.SDA.Mask2Out

ClearSweeps	Action
View	Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SDA.Mask2Out.Out.Result

MASKHITS app.SDA.MaskHits

ClearSweeps	Action
View	Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SDA.MaskHits.Out.Result

MASKOUT app.SDA.MaskOut

ClearSweeps	Action
View	Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

View Book

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SDA.MaskOut.Out.Result

PRBS app.SDA.PRBS

AxisXRotation	Integer
AxisYRotation	Integer
ClearSweeps	Action
LabelsPosition	String
LabelsText	String
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
RiseTime	Double
ShowLastTrace	Bool
SignalFrequency	Double
UseGrid	String
View	Bool
ViewLabels	Bool

AxisXRotation Integer

Range From -90 to 90 step 1

Description

Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx.

AxisYRotation Integer From -90 to 90 step 1 Range Description Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx. **ClearSweeps** Action Description Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx. LabelsPosition String Any number of characters Range Description Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx. LabelsText String Any number of characters Range Description Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx. Enum Persist3DQuality Description Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx. **Values** Shaded Solid WireFrame **Persisted** Bool Description Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx. Bool Persistence3d Description Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx. **PersistenceMonoChrome** Bool Description Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx. **PersistenceSaturation** Integer From 0 to 100 step 1 Range Description Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx.

PersistenceTime Enum

Description

Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx.

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

RiseTime Double

Range From 1e-015 to 1 step 1e-015

Description

Sets/Queries the rise time of the signal.

RiseTime = app.SDA.PRBS.RiseTime

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Inspect the rise time of the signal.
```

ShowLastTrace Bool

Description

Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx.

SignalFrequency Double

Range From 90000 to 4e+010 step 1

Description

Please see the corresponding variable in app.Measure.Px.Operator (ParamEngine = "Dperiod@level").

UseGrid String

Range Any number of characters

Description

Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx.

View Book

Description

Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx.

ViewLabels Bool

Description

Using SDA.PRBS, please refer to the corresponding variable in Acquisition.Cx.

RESULT

app.SDA.PRBS.Out.Result

Properties of the type xxxx.Out.Result.yyyy are those of the last completed acquisition. They are not affected if other cvars are changed after that acquisition was completed. This distinction between "Out.Result" properties and other cvars is most important when the trigger mode is Single or Stopped. You should treat "Out.Result" properties as read-only.

SDASTATUS

app.SDA.SDAStatus

DataSource	Enum
SignalFrequency	Double

DataSource Enum

Values

SignalFrequency Double

Range From 90000 to 4e+010 step 1

TIE app.SDA.TIE

ClearSweeps	Action
ClockModeOn	Bool

CompensateForMissingEdges	Bool
CustomPLLTransportDelay	Double
Deskew	Double
EyeThresholdType	Enum
IntervalsEdgeEdge	Integer
PermitGTHalfUI	Bool
PLLType	Enum
ReferenceFrequency	Double
RefPercentLevel	Double
RefThresholdType	Enum
SDAMode	Enum
SignalFrequency	Double
TIEPercentLevel	Double
TIESlope	Enum
UseAllEdges	Bool
View	Bool

Clear Sweeps

Description
Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

ClockModeOn

CompensateForMissingEdges

Bool

CustomPLLTransportDelay
Range From 0 to 1 step 1e-015

Deskew

Double

EyeThresholdType

Enum

Description

Sets/Queries whether the eye threshold is measured in absolute units or percentage.

Example

Range

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the eye threshold to percent.
app.SDA.TIE.EyeThresholdType = "Absolute"
```

From -1e-008 to 1e-008 step 1e-012

Values

Absolute	
Percent	

IntervalsE	EdgeEdge		Integer
Range	From 1 to 100000 sto	ер 1	
PermitGT	HalfUl		Вооі
PLLType			Enum
Values			
Values	Custom		
	DVI		
	FBDIMM		
	GOLDEN		
	PCIEXPRESS		
Reference	eFrequency		Double
Range	From 90000 to 4e+0	10 step 1	
RefPerce	ntLevel		Double
Range	From 0 to 100 step 1		
RefThres	holdType		Enum
Values			
	Absolute		
	Percent		
SDAMode)		Enum
Values			
	MaskTest		
	Scope		
SignalFre	equency		Double
Range	From 90000 to 4e+0	10 step 1	
Descrip	tion		
Sets	/Queries the signal free	quency for TIE.	
Exampl	e		
	isual Basic Scrip app = CreateObje	t ct("LeCroy.XStreamDSO")	
	et the signal fre .SDA.TIE.SignalFr	quency to 2.00 MHz equency = 2.0e6	
TIEPerce	ntLevel		Double
Range	From 0 to 100 step 1		

TIESlope Enum

Values

Both	
Neg	
Pos	

UseAllEdges Book

View Bool

Description

Sets/Queries the visibility of the function.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Show the TIE function.
app.SDA.TIE.View = True
```

RESULT

app.SDA.TIE.Out.Result

Properties of the type xxxx.Out.Result.yyyy are those of the last completed acquisition. They are not affected if other cvars are changed after that acquisition was completed. This distinction between "Out.Result" properties and other cvars is most important when the trigger mode is Single or Stopped. You should treat "Out.Result" properties as read-only.

TIEF app.SDA.TIEF

BitRate	Double
ClearSweeps	Action
View	Bool

BitRate Double

Range From 90000 to 4e+010 step 1

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SDA.TIEF.Out.Result

SERIALDECODE

app.SerialDecode

The Serial Decode Tab is the entry point for all of the decoders supported in LeCroy scopes

AnnotationPositionPreference	Enum
LinkedToTrigger1	Bool
LinkedToTrigger2	Bool
LinkedToTrigger3	Bool
LinkedToTrigger4	Bool
SelectDecoder	Enum

Annota	ationPositionPreference	Enum
Valu	lues	
	OnNoisyTrace	
	OnTrace	
Linked	dToTrigger1	Воог
Linked	dToTrigger2	Воог
Linked	dToTrigger3	Воог
Linked	dToTrigger4	Воог
Select	Decoder	Enum
Valu	lues	
	Decode1	
	Decode2	
	Decode3	
	Decode4	

8B10B

app.SerialDecode.Decode[n].Protocol (Protocol = "8B10B")

BitRate	Double
ColumnState	String
FilteredSymbolList	String
LevelPercent	Double
LevelType	Enum
PrimitiveFile	FileName
PrimitiveSource	Enum

	ViewingMode		Enum	
BitRate				Double
Range	From 1000 to 1e+010 ste	ep 0.0001		
olumnSt	ate			String
Range	Any number of character	S		
ilteredSy	/mbolList			String
Range	Any number of character	S		
evelPerc	ent			Double
Range	From 0 to 100 step 0.1			
evelType	;			Enum
Values				
	Absolute			
	Percent			
rimitiveF	File			FileName
Range	Any number of character	s		
rimitiveS	Source			Enum
Values				
	8b10b			
	Others			
	PCIE			
	PCIE20			
	SAS			
	SATA			
	USB3			
	XAUI			
iewingM	ode			Enum
Values				
	Hexadecimal			
	Symbolic			
AUDIO	I2S	app.SerialDecode.Decode[n].P	rotocol (Protocol	= "Audiol2S
	Annotate		Enum	

BitOrder	Enum
BitsInChannel	Integer
BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum
ClockPhase	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSOffset	Integer
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
IgnoreCS	Bool
MinSamplesPerBit	Integer
ViewingMode	Enum

Annotate		Enum
Values		
	All	
	Left	
	Right	
BitOrder		Enum
Values		
	LSB	
	MSB	
BitsInCha	nnel	Integer
Range	From 1 to 32 step 1	
BitsPerBy	rte	Integer
Range	From 2 to 32 step 1	

ByteSlice	l	Enum
Values		
	CSbased	
	CSbasedMulti	
	HolebasedMulti	
	NoHole	
	Std	
	UserCol	
ClockLev	elPercent	Double
Range	From 0 to 100 step 0.1	
ClockLev	elType	Enum
Values		
	Absolute	
	Percent	
ClockPha	se	Enum
Values		
	Negative	
	Positive	
ColumnS	tate	String
Range	Any number of characters	
Conversion	on	Enum
Values		
	Binary	
	Binary2Cpl	
CSLevelP	Percent	Double
Range	From 0 to 100 step 0.1	
CSLevelT	уре	Enum
Values		
	Absolute	
	Percent	

CSLockN	lode	Enum
Values		
	Falling	
	Rising	
CSOffset		Integer
Range	From 0 to 31 step 1	
CSPolarit	ty	Enum
Values		
	ActiveHigh	
	ActiveLow	
DataLeve	lPercent	Double
Range	From 0 to 100 step 0.1	
DataLeve	Туре	Enum
Values		
	Absolute	
	Percent	
IgnoreCS	 	Воог
MinSamp	lesPerBit	Integer
Range	From 4 to 100 step 1	
ViewingN	lode	Enum
Values		
	Binary	
	dB	
	Dec	

AUDIOLJ

 $app. Serial Decode. Decode[n]. Protocol\ (Protocol = "AudioLJ")$

Annotate	Enum
BitOrder	Enum
BitsInChannel	Integer
BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum

ClockPhase	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSOffset	Integer
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
IgnoreCS	Bool
MinSamplesPerBit	Integer
ViewingMode	Enum

Annotate		Enum
Values		
	All	
	Left	
	Right	
BitOrder		Enum
Values		
	LSB	
	MSB	
BitsInCha	nnel	Integer
Range	From 1 to 32 step 1	
BitsPerBy	rte	Integer
Range	From 2 to 32 step 1	
ByteSlice	r	Enum
Values		
	CSbased	
	CSbasedMulti	
	HolebasedMulti	
	NoHole	
	Std	
	UserCol	
Clockl av	elPercent	Double

Range From 0 to 100 step 0.1

ClockLev	elType		Enum
Values			
	Absolute		
	Percent		
ClockPha	ISE		Enum
Values			
	Negative		
	Positive		
ColumnS	tate		String
Range	Any number of chara	cters	
Conversi	on		Enum
Values			
	Binary		
	Binary2Cpl		
CSLevelP Range	Percent From 0 to 100 step 0	.1	Double
CSLevelT	уре		Enum
Values			
	Absolute		
	Percent		
CSLockM	lode		Enum
Values			
	Falling		
	Rising		
CSOffset			Integer
Range	From 0 to 31 step 1		
CSPolarit	y		Enum
Values			
	ActiveHigh		
	ActiveLow		

DataLeve	Double	
Range	From 0 to 100 step 0.1	
DataLeve	lType	Enum
Values		
	Absolute	
	Percent	
IgnoreCS		Вооі
MinSamp	lesPerBit	Integer
Range	From 4 to 100 step 1	
ViewingN	lode	Enum
Values		
	Binary	
	dB	
	Dec	
	Hex	

AUDIORJ

app.SerialDecode.Decode[n].Protocol (Protocol = "AudioRJ")

Annotate	Enum
BitOrder	Enum
BitsInChannel	Integer
BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum
ClockPhase	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSOffset	Integer
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
IgnoreCS	Bool
MinSamplesPerBit	Integer
ViewingMode	Enum

Values	All Left	
	Left	
<u> </u>	Loit	
	Right	
BitOrder		Enum
Values		
	LSB	
	MSB	
BitsInCha	nnel	Integer
Range	From 1 to 32 step 1	
BitsPerBy	te	Integer
Range	From 2 to 32 step 1	
ByteSlicer		Enum
Values		
	CSbased	
	CSbasedMulti	
	HolebasedMulti	
	NoHole	
	Std	
	UserCol	
ClockLeve	lPercent	Double
Range	From 0 to 100 step 0.1	
ClockLeve	lType	Enum
Values		
	Absolute	
	Percent	
ClockPhas	5 e	Enum
Values		
	Negative	
	Positive	
ColumnSt	ate	String
Range	Any number of characters	

Conversion	on	Enum
Values		
	Binary	
	Binary2Cpl	
CSLevelP	ercent	Double
Range	From 0 to 100 step 0.1	
CSLevelT	ype	Enum
Values		
	Absolute	
-	Percent	
CSLockM	ode	Enum
Values		
	Falling	
	Rising	
CSOffset		Integer
Range	From 0 to 31 step 1	
CSPolarity	/	Enum
Values		
	ActiveHigh	
	ActiveLow	
DataLevel	Percent	Double
Range	From 0 to 100 step 0.1	
DataLevel	Туре	Enum
Values		
	Absolute	
	Percent	
IgnoreCS		Вооі
MinSampl	esPerBit	Integer
Range	From 4 to 100 step 1	

ViewingMode Enum

Values

Binary	
dB	
Dec	
Hex	

AUDIOTDM

app.SerialDecode.Decode[n].Protocol (Protocol = "AudioTDM")

Annotate	Enum
BitOrder	Enum
BitsInChannel	Integer
BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum
ClockPhase	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSOffset	Integer
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
IgnoreCS	Bool
MinSamplesPerBit	Integer
ViewingMode	Enum

Annotate Enum

Values

All	
Audio1	
Audio2	
Audio3	
Audio4	
Audio5	
Audio6	
Audio7	
Audio8	

BitOrder			Enum
Values	.		
	LSB		
	MSB		
BitsInCha	annel		Integer
Range	From 1 to 32 step 1		
BitsPerB	yte		Integer
Range	From 2 to 32 step 1		
ByteSlice			Enum
Values	•		
	CSbased		
	CSbasedMulti		
	HolebasedMulti		
	NoHole		
	Std		
	UserCol		
Clockl ev	elPercent	· · · · · · · · · · · · · · · · · · ·	Double
Range	From 0 to 100 step 0	1	
Nange	1 10111 0 10 100 0100 0	••	
ClockLev	elType		Enum
Values	· · · · · · · · · · · · · · · · · · ·		
	Absolute		
	Percent		
ClockPha	ise		Enum
Values			
Values	Negative		
	Positive		
ColumnS	tate		String
Range	Any number of chara	cters	
			<u>-</u>
Conversi	on		Enum
Values	;		
	Binary		
	Binary2Cpl		
	·		

CSLevelP	ercent	Double
Range	From 0 to 100 step 0.1	
CSLevelT	уре	Enum
Values		
	Absolute	
	Percent	
CSLockM	ode	Enum
Values		
	Falling	
	Rising	
CSOffset		Integer
Range	From 0 to 31 step 1	
CSPolarity	y	Enum
Values		
	ActiveHigh	
	ActiveLow	
DataLevel	Percent	Double
Range	From 0 to 100 step 0.1	
DataLevel	Туре	Enum
Values		
	Absolute	
	Percent	
IgnoreCS		Вооі
MinSampl	esPerBit	Integer
Range	From 4 to 100 step 1	
ViewingM	ode	Enum
Values		
	Binary	
	dB	
	Dec	
	Hex	

app.SerialDecode.Decode[n].Protocol (Protocol = "CAN")

BitRate	Double
ColumnState	String
dbLibFile	FileName
GMLAN	Bool
LevelPercent	Double
LevelType	Enum
ShowStuffBits	Bool
Tolerance	Double
ViewingMode	Enum

BitRate							Double
Range	From 10 to 2e+007	step 1					
ColumnS	tate						String
Range	Any number of cha	racters					
dbLibFile							FileName
Range	Any number of cha	racters					
GMLAN							Bool
LevelPerd	cent						Double
Range	From 0 to 100 step	0.1					
LevelType	e						Enum
Values							
	Absolute						
	Percent						
ShowStu	ffBits						Bool
Tolerance							Double
Range	From 0.01 to 10 ste	ep 0.01					
ViewingN	lode						Enum
Values							
	Hexadecimal						
	Symbolic						
CANHI	_		app.Seri	alDecode.Dec	ode[n].Prot	ocol (Protoco	ol = "CANHL"
	BitRate					Double	

ColumnState	String
dbLibFile	FileName
GMLAN	Bool
LevelPercent	Double
LevelType	Enum
ShowStuffBits	Bool
Tolerance	Double
ViewingMode	Enum

BitRate		Double
Range	From 10 to 2e+007 step 1	
ColumnS	itate	String
Range	Any number of characters	
dbLibFile	}	FileName
Range	Any number of characters	
GMLAN		Вооі
LevelPer	cent	Double
Range	From 0 to 100 step 0.1	
LevelTyp	e	Enum
Values	;	
	Absolute	
	Percent	
ShowStu	ffBits	Вооі
Tolerance	e	Double
Range	From 0.01 to 10 step 0.01	
ViewingN	/lode	Enum
Values	3	
	Hexadecimal	

FLX

 $app. Serial Decode. Decode[n]. Protocol\ (Protocol = "FLX")$

BitRate	Double
Channel	Enum
ColumnState	String

LevelHighPercent	Double
LevelHighType	Enum
LevelLowPercent	Double
LevelLowType	Enum
Tolerance	Double
ViewingMode	Enum

BitRate			Double
Range	From 1e+006 to 2e-	-007 step 1000	
Channel			Enum
Values			
3 0.1.0.00	Α		
	В		
ColumnS	tate		String
Range	Any number of char	acters	
LevelHigh	nPercent		Double
Range	From 0 to 100 step	0.1	
LevelHigh	ıType		Enum
Values			
	Absolute		
	Percent		
LevelLow	Percent		Double
Range	From 0 to 100 step	0.1	
LevelLow	Туре		Enum
Values			
	Absolute		
	Percent		
Tolerance)		Double
Range	From 0.01 to 10 ste	p 0.01	
Viewing N	lode		Enum
Values			
	Hex		
	Symbolic		
Values	Hex		

GMCANHL

app.SerialDecode.Decode[n].Protocol (Protocol = "GMCANHL")

BitRate	Double
ColumnState	String
dbLibFile	FileName
GMLAN	Bool
LevelPercent	Double
LevelType	Enum
ShowStuffBits	Bool
Tolerance	Double
ViewingMode	Enum

BitRate		Double
Range	From 10 to 2e+007 step 1	
ColumnS	itate	String
Range	Any number of characters	
dbLibFile	}	FileName
Range	Any number of characters	
GMLAN		Вооі
LevelPerd	cent	Double
Range	From 0 to 100 step 0.1	
LevelTyp	e	Enum
Values		
	Absolute	
	Percent	
ShowStu	ffBits	Bool
Tolerance	e	Double
Range	From 0.01 to 10 step 0.01	
ViewingN	/lode	Enum
Values	;	
	Hexadecimal	
	Symbolic	
	<u> </u>	

GMCANLAN

app.SerialDecode.Decode[n].Protocol (Protocol = "GMCANLAN")

BitRate	Double
ColumnState	String
dbLibFile	FileName
GMLAN	Bool
LevelPercent	Double
LevelType	Enum
ShowStuffBits	Bool
Tolerance	Double
ViewingMode	Enum

BitRate			Double
Range	From 10 to 2e+007 s	ep 1	
ColumnS	tate		String
Range	Any number of chara	eters	
dbLibFile			FileName
Range	Any number of chara	eters	
GMLAN			Bool
LevelPerd	cent		Double
Range	From 0 to 100 step 0	1	
LevelType	e		Enum
Values			
	Absolute		
	Percent		
ShowStu	ffBits		Bool
Tolerance	 9		Double
Range	From 0.01 to 10 step	0.01	
ViewingN	lode		Enum
Values			
	Hexadecimal		
	Symbolic		
I2C		app.SerialDecode.Decode[n].Protoco	(Protocol = "I2C"
	AddressWithRW	Воо	
	7100100077111111111		

BitRate	Double
ClockLevelPercent	Double
ClockLevelType	Enum
ColumnState	String
DataLevelPercent	Double
DataLevelType	Enum
Tolerance	Double
ViewingMode	Enum

Address\	WithRW	Воог
BitRate		Double
Range	From 10 to 2e+006 step 1	
ClockLev	velPercent	Double
Range	From 0 to 100 step 0.1	
ClockLev	velType	Enum
Values	S	
	Absolute	
	Percent	
ColumnS	State	String
Range	Any number of characters	
DataLeve	elPercent	Double
Range	From 0 to 100 step 0.1	
DataLeve	еІТуре	Enum
Values	S	
	Absolute	
	Percent	
Toleranc	e	Double

Range From 0.01 to 10 step 0.01

ViewingM	ode		Enum
Values			
	ASCII		
	Binary		
	Dec		
	Hex		
LIN		app.SerialDecode.Decode[n].Protocol	(Protocol = "LIN")
			7
	BitRate ColumnState	Double	_
	LevelPercent	String Double	_
	LevelType	Enum	_
	LINVersion	Enum	-
	Tolerance	Double	
BitRate			Double
Range	From 1000 to 20000	step 1	
ColumnSt	ate		String
Range	Any number of chara	cters	
LevelPerc	ent		Double
Range	From 0 to 100 step 0	.1	
LevelType	•		Enum
Values			
	Absolute		
	Percent		
LINVersio	n		Enum
Values			
	ALL		
	J2602		
	Rev1.3		
	Rev2.x		
Tolerance			Double
	From 0.01 to 10 step	0.01	
Range	. τοιπ σ.στ το το στερ		

MIL1553

 $app. Serial Decode. Decode[n]. Protocol\ (Protocol = "MIL1553")$

BitRate	Double
ColumnState	String
FBO	Double
HalfSyncWidth	Double
LevelHAbsolute	Double
LevelHType	Enum
LevelLAbsolute	Double
LevelLType	Enum
MinSamplesPerBit	Integer
NPproximity	Double
TableMode	Enum
ViewingMode	Enum

BitRate			Double		
Range	From 1000 to 2e+00	7 step 50			
ColumnS	tate		String		
Range	Any number of chara	acters			
FBO			Double		
Range	From 0 to 50 step 0.1				
HalfSync	Width		Double		
Range	From 4e-008 to 0.02	5 step 1e-008			
LevelHAbsolute			Double		
Range	From -10 to 10 step	om -10 to 10 step 0.05			
LevelHTy	pe		Enum		
Values	· ·				
	Absolute				
	Percent				
LevelLAb	solute		Double		
Range	From -10 to 10 step 0.05				
LevelLTy	pe		Enum		
Values					
	Absolute				
	Percent				

MinSamplesPerBit		Integer
Range	From 4 to 100 step 1	
NPproxim	nity	Double
Range	From 1e-009 to 0.005 step 1e-009	
TableMod	le	Enum
Values		
	Transfer	
	Word	
ViewingM	lode	Enum
Values		
	Binary	
•	Hex	

PCIE1X1

app.SerialDecode.Decode[n].Protocol (Protocol = "PCIE1X1")

BitRate	Double
CurrentBitRate	Double
InputIsDescrambled	Bool
Lane	Integer
LevelPercent	Double
LevelType	Enum
LinkToProtoColAnalyzer	Bool
ScramblingOn	Bool
SpeedChangeAt	Double
ViewMode	Enum

BitRate		Double
Range	From 1e+008 to 2e+010 step 1000	
CurrentB	itRate	Double
Range	From 1e+008 to 2e+010 step 1000	
InputIsDe	scrambled	Вооі
Lane		Integer
Range	From 0 to 15 step 1	

LevelPerd	ent	Double
Range	From 0 to 100 step 0.1	
LevelType)	Enum
Values		
	Absolute	
	Percent	
LinkToPro	otoColAnalyzer	Вооі
Scramblin	ngOn	Вооі
SpeedCha	angeAt	Double
Range	From -100 to 100 step 1e-009	
ViewMode	e	Enum
Values		

PCIE1X2

app.SerialDecode.Decode[n].Protocol (Protocol = "PCIE1X2")

BitRate	Double
CurrentBitRate	Double
InputIsDescrambled	Bool
Lane	Integer
LevelPercent	Double
LevelType	Enum
LinkToProtoColAnalyzer	Bool
ScramblingOn	Bool
SpeedChangeAt	Double
ViewMode	Enum

BitRate		Double
Range	From 1e+008 to 2e+010 step 1000	
CurrentBi	tRate	Double
Range	From 1e+008 to 2e+010 step 1000	
InputIsDe	scrambled	Вооі
Lane		Integer
Range	From 0 to 15 step 1	

		,	
LevelPerd	ent		Double
Range	From 0 to 100 step 0.1		
LevelType	;		Enum
Values			
	Absolute		
	Percent		
LinkToPr	otoColAnalyzer		Bool
Scramblii	ngOn		Bool
SpeedCh	angeAt		Double
Range	From -100 to 100 step 1e-009		
ViewMod	• •		Enum
Values			

PCIE4X1

app.SerialDecode.Decode[n].Protocol (Protocol = "PCIE4X1")

BitRate	Double
CurrentBitRate	Double
InputIsDescrambled	Bool
LevelPercent	Double
LevelType	Enum
LinkToProtoColAnalyzer	Bool
ScramblingOn	Bool
SpeedChangeAt	Double
ViewMode	Enum

BitRate		Double
Range	From 1e+008 to 2e+010 step 1000	
CurrentBi	tRate	Double
Range	From 1e+008 to 2e+010 step 1000	
InputIsDe	scrambled	Вооі
LevelPerd	cent	Double
Range	From 0 to 100 step 0.1	

LevelType	9		Enum
Values			
	Absolute		
	Percent		
LinkToPro	otoColAnalyzer		Bool
Scramblir	ngOn		Bool
SpeedCha	angeAt		Double
Range	From -100 to 100 step 1e-00	09	
ViewMod	e		Enum
Values			
RS232		app.SerialDecode.Decode[n].Protocol (Proto	ocol = "RS232
	BitRate	Double	
	ByteOrderUI	Enum	
	ColumnState	String	
	DataBitsUI	Integer	
	LevelPercent	Double	
	LevelType	Enum	
	Parity	Enum	
	ParityUI	Enum	
	PolarityUI	Enum	
	StopBitsUI	Enum	
	Tolerance	Double	
	ViewingMode	Enum	
BitRate			Double
Range	From 30 to 5e+008 step 1		
ByteOrde	rUI		Enum
Values			
	LSB		
	MSB		
ColumnS	tate		String
Range	Any number of characters		

DataBitsl	UI	Integer
Range	From 5 to 16 step 1	
LevelPer	cent	Double
Range	From 0 to 100 step 0.1	
LevelTyp	pe	Enum
Values		
Values	Absolute	
	Percent	
Dority		Enum
Parity		Liidiii
Values	5	
	Even	
	Mark	
	None	
	Odd	
	Space	
ParityUl		Enum
Values	5	
	Even	
	None	
	Odd	
PolarityU		Enum
Values	S	
	IdleHigh	
	IdleLow	
StopBits	UI	Enum
Malaaa	_	
Values		
	1	
	2	
Tolerance	е	Double
Range	From 0.01 to 10 step 0.01	

ViewingMode Enum

Values

ASCII	
Binary	
Hex	

SIOP

app.SerialDecode.Decode[n].Protocol (Protocol = "SIOP")

BitOrder	Enum
BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum
ClockPhase	Enum
ClockPolarity	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
DDR	Bool
IgnoreCS	Bool
InterFrameSetup	Enum
InterFrameTime	Double
MinSamplesPerBit	Integer
TDMChannel	Integer
ViewingMode	Enum

BitOrder		Enun

Values

LSB	
MSB	

BitsPerByte Integer

Range From 2 to 32 step 1

ByteSlice	r	Enum
Values		
	CSbased	
	CSbasedMulti	
•	HolebasedMulti	
	NoHole	
	Std	
	UserCol	
ClockLev	elPercent	Double
Range	From 0 to 100 step 0.1	
ClockLev	elType	Enum
Values		
	Absolute	
	Percent	
ClockPha	se	Enum
Values		
	0	
	1	
ClockPola	arity	Enum
Values		
	0	
	1	
ColumnS	tate	String
Range	Any number of characters	
Conversion	 on	Enum
Values		
	Binary	
	Binary2Cpl	
CSLevelP	ercent	Double
Range	From 0 to 100 step 0.1	

CSLevelT	уре	Enum
Values		
	Absolute	
	Percent	
CSLockM	lode	Enum
Values		
	Both	
	Falling	
	Rising	
CSPolarit	у	Enum
Values		
	ActiveHigh	
	ActiveLow	
DataLeve	IPercent	Double
Range	From 0 to 100 step 0.1	
DataLeve	ІТуре	Enum
Values		
	Absolute	
	Percent	
DDR		Вооі
IgnoreCS		Вооі
InterFram	neSetup	Enum
Values		
	Auto	
	Manual	
InterFram	neTime	Double
Range	From 1e-009 to 10 step 1e-009	
MinSamp	lesPerBit	Integer
Range	From 4 to 100 step 1	
TDMChar		Integer
Range	From 1 to 8 step 1	

ViewingMode Enum

Values

ASCII	
Binary	
Dec	
Hex	

SPI

app.SerialDecode.Decode[n].Protocol (Protocol = "SPI")

BitOrder	Enum
BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum
ClockPhase	Enum
ClockPolarity	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
DDR	Bool
IgnoreCS	Bool
InterFrameSetup	Enum
InterFrameTime	Double
MinSamplesPerBit	Integer
TDMChannel	Integer
ViewingMode	Enum

BitOrder	<u>En</u>
BitOrder	Er i

Values

LSB	
MSB	

BitsPerByte Integer

Range From 2 to 32 step 1

ByteSlice	er	Enum
Values		
	CSbased	
	CSbasedMulti	
	HolebasedMulti	
	NoHole	
	Std	
	UserCol	
ClockLev	relPercent	Double
Range	From 0 to 100 step 0.1	
ClockLev	relType	Enum
Values	:	
	Absolute	
	Percent	
ClockPha	ase	Enum
Values	}-	
	0	
	1	
ClockPol	arity	Enum
Values	;	
	0	
	1	
ColumnS	itate	String
Range	Any number of characters	_
Nange	Any number of characters	
Conversion	on	Enum
Values		
	Binary	
	Binary2Cpl	
CSLevelP	Percent	Double
Range	From 0 to 100 step 0.1	

CSLevelT	уре	Enum
Values		
	Absolute	
	Percent	
CSLockM	lode	Enum
Values		
	Both	
	Falling	
	Rising	
CSPolarit	у	Enum
Values		
	ActiveHigh	
	ActiveLow	
DataLeve	IPercent	Double
Range	From 0 to 100 step 0.1	
DataLeve	ІТуре	Enum
Values		
	Absolute	
	Percent	
DDR		Вооі
IgnoreCS		Вооі
InterFram	neSetup	Enum
Values		
	Auto	
	Manual	
InterFram	neTime	Double
Range	From 1e-009 to 10 step 1e-009	
MinSamp	lesPerBit	Integer
Range	From 4 to 100 step 1	
TDMChar		Integer
Range	From 1 to 8 step 1	

ViewingMode Enum

Values

ASCII	
Binary	
Dec	
Hex	

SPICUSTOM

app.SerialDecode.Decode[n].Protocol (Protocol = "SPICustom")

BitOrder	Enum
BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum
ClockPhase	Enum
ClockPolarity	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
DDR	Bool
IgnoreCS	Bool
InterFrameSetup	Enum
InterFrameTime	Double
MinSamplesPerBit	Integer
TDMChannel	Integer
ViewingMode	Enum

BitOrder	Enun

Values

LSB	
MSB	

BitsPerByte Integer

Range From 2 to 32 step 1

ByteSlice	r	Enum
Values		
	CSbased	
	CSbasedMulti	
	HolebasedMulti	
	NoHole	
	Std	
	UserCol	
ClockLev	elPercent	Double
Range	From 0 to 100 step 0.1	
ClockLev	elType	Enum
Values		
	Absolute	
	Percent	
ClockPha	ise	Enum
Values		
	0	
	1	
ClockPola	arity	Enum
Values		
	0	
	1	
ColumnS	tate	String
Range	Any number of characters	
Conversion	on	Enum
Values		
	Binary	
	Binary2Cpl	
CSLevelP	Percent	Double
Range	From 0 to 100 step 0.1	

CSLevelT	Гуре	Enum
Values		
	Absolute	
	Percent	
CSLockM	lode	Enum
Values		
	Both	
	Falling	
	Rising	
CSPolarit	ty	Enum
Values		
	ActiveHigh	
	ActiveLow	
DataLeve	elPercent	Double
Range	From 0 to 100 step 0.1	
DataLeve	elType	Enum
Values		
	Absolute	
	Percent	
DDR		Вооі
IgnoreCS		Вооі
InterFram	neSetup	Enum
Values		
	Auto	
	Manual	
InterFram	neTime	Double
Range	From 1e-009 to 10 step 1e-009	
MinSamp	elesPerBit	Integer
Range	From 4 to 100 step 1	
TDMChan	nnel	Integer
Range	From 1 to 8 step 1	

ViewingMode Enum

Values

ASCII	
Binary	
Dec	
Hex	

SPIDDR

app.SerialDecode.Decode[n].Protocol (Protocol = "SPIDDR")

BitOrder	Enum
BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum
ClockPhase	Enum
ClockPolarity	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
DDR	Bool
IgnoreCS	Bool
InterFrameSetup	Enum
InterFrameTime	Double
MinSamplesPerBit	Integer
TDMChannel	Integer
ViewingMode	Enum

BitOrder	Enum
Values	

LSB	
MSB	

BitsPerByte Integer

Range From 2 to 32 step 1

ByteSlice	r	Enum
Values		
	CSbased	
	CSbasedMulti	
•	HolebasedMulti	
	NoHole	
	Std	
	UserCol	
ClockLev	elPercent	Double
Range	From 0 to 100 step 0.1	
ClockLev	elType	Enum
Values		
	Absolute	
	Percent	
ClockPha	se	Enum
Values		
	0	
	1	
ClockPola	arity	Enum
Values		
	0	
	1	
ColumnS	tate	String
Range	Any number of characters	
Conversion	 on	Enum
Values		
	Binary	
	Binary2Cpl	
CSLevelP	ercent	Double
Range	From 0 to 100 step 0.1	

CSLevelT	Гуре	Enum
Values		
	Absolute	
	Percent	
CSLockM	lode	Enum
Values		
	Both	
	Falling	
	Rising	
CSPolarit	ty	Enum
Values		
	ActiveHigh	
	ActiveLow	
DataLeve	elPercent	Double
Range	From 0 to 100 step 0.1	
DataLeve	elType	Enum
Values		
	Absolute	
	Percent	
DDR		Вооі
IgnoreCS		Вооі
InterFram	neSetup	Enum
Values		
	Auto	
	Manual	
InterFram	neTime	Double
Range	From 1e-009 to 10 step 1e-009	
MinSamp	elesPerBit	Integer
Range	From 4 to 100 step 1	
TDMChan	nnel	Integer
Range	From 1 to 8 step 1	

ViewingMode Enum

Values

ASCII	
Binary	
Dec	
Hex	

SSPI

app.SerialDecode.Decode[n].Protocol (Protocol = "SSPI")

BitOrder	Enum
BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum
ClockPhase	Enum
ClockPolarity	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
DDR	Bool
IgnoreCS	Bool
InterFrameSetup	Enum
InterFrameTime	Double
MinSamplesPerBit	Integer
TDMChannel	Integer
ViewingMode	Enum

BitOrder	Enum
----------	------

Values

LSB	
MSB	

BitsPerByte Integer

Range From 2 to 32 step 1

ByteSlice	r	Enum
Values		
	CSbased	
•	CSbasedMulti	
•	HolebasedMulti	
	NoHole	
	Std	
	UserCol	
ClockLev	elPercent	Double
Range	From 0 to 100 step 0.1	
ClockLev	elType	Enum
Values		
	Absolute	
	Percent	
ClockPha	se	Enum
Values		
	0	
	1	
ClockPola	arity	Enum
Values		
	0	
	1	
ColumnS	tate	String
Range	Any number of characters	
Conversion	 on	Enum
Values		
	Binary	
	Binary2Cpl	
CSLevelP	ercent	Double
Range	From 0 to 100 step 0.1	

CSLevelT	Гуре	Enum
Values		
	Absolute	
	Percent	
CSLockM	lode	Enum
Values		
	Both	
	Falling	
	Rising	
CSPolarit	ty	Enum
Values		
	ActiveHigh	
	ActiveLow	
DataLeve	elPercent	Double
Range	From 0 to 100 step 0.1	
DataLeve	elType	Enum
Values		
	Absolute	
	Percent	
DDR		Вооі
IgnoreCS		Вооі
InterFram	neSetup	Enum
Values		
	Auto	
	Manual	
InterFram	neTime	Double
Range	From 1e-009 to 10 step 1e-009	
MinSamp	elesPerBit	Integer
Range	From 4 to 100 step 1	
TDMChan	nnel	Integer
Range	From 1 to 8 step 1	

ViewingMode Enum

Values

ASCII	
Binary	
Dec	
Hex	

UART

app.SerialDecode.Decode[n].Protocol (Protocol = "UART")

	T
BitRate	Double
ByteOrderUI	Enum
ColumnState	String
DataBitsUI	Integer
LevelPercent	Double
LevelType	Enum
Parity	Enum
ParityUI	Enum
PolarityUI	Enum
StopBitsUI	Enum
Tolerance	Double
ViewingMode	Enum

BitRate		Double
Range	From 30 to 5e+008 step 1	
ByteOrde	rUI	Enum
Values		
	LSB	
	MSB	
ColumnSt	ate	String
Range	Any number of characters	
DataBitsU		Integer
Range	From 5 to 16 step 1	
LevelPerc	ent	Double
Range	From 0 to 100 step 0.1	

LevelType	9		Enum
Values			
	Absolute		
	Percent		
Parity			Enum
Values			
	Even		
	Mark		
	None		
	Odd		
	Space		
ParityUI			Enum
Values			
	Even		
	None		
	Odd		
PolarityU	 		Enum
Values			
	IdleHigh		
	IdleLow		
StopBitsl	JI		Enum
Values			
	1		
	2		
Tolerance			Double
Range	From 0.01 to 10 step 0.0	01	
Nange	1 10111 0:01 10 10 3100 0:0		
ViewingN	lode		Enum
Values			
	ASCII		
	Binary		
	Hex		
USAR1	r	app.SerialDecode.Decode[n].Protocol (Protoc	col = "USART")
	•	,,,,,	<u> </u>
	BitOrder	Enum	

BitsPerByte	Integer
ByteSlicer	Enum
ClockLevelPercent	Double
ClockLevelType	Enum
ClockPhase	Enum
ClockPolarity	Enum
ColumnState	String
Conversion	Enum
CSLevelPercent	Double
CSLevelType	Enum
CSLockMode	Enum
CSPolarity	Enum
DataLevelPercent	Double
DataLevelType	Enum
DDR	Bool
IgnoreCS	Bool
InterFrameSetup	Enum
InterFrameTime	Double
MinSamplesPerBit	Integer
TDMChannel	Integer
ViewingMode	Enum

BitOrder		Enum
Values		
	LSB	
	MSB	
BitsPerBy	yte	Integer
Range	From 2 to 32 step 1	
ByteSlice	er	Enum
Values		
	CSbased	

Std UserCol Double

Range From 0 to 100 step 0.1

CSbasedMulti HolebasedMulti

NoHole

ClockLev	velType		Enum
Values	5		
	Absolute		
	Percent		
ClockPha	ase		Enum
Values	5		
	0		
	1		
ClockPol	arity		Enum
Values	5		
	0		
	1		
ColumnS	State		String
Range	Any number of chara	cters	
Conversi	on		Enum
Values	5		
	Binary		
	Binary2Cpl		
CSLevelF	Percent		Double
Range	From 0 to 100 step 0	.1	
CSLevel7	Гуре		Enum
Values	5		
	Absolute		
	Percent		
CSLockN	Mode		Enum
Values	5		
	Both		
	Falling		
	Rising		

CSPolarit	у	Enum
Values		
	ActiveHigh	
	ActiveLow	
DataLeve	lPercent	Double
Range	From 0 to 100 step 0.1	
DataLeve	ІТуре	Enum
Values		
	Absolute	
	Percent	
DDR		Bool
gnoreCS		Bool
InterFram	neSetup	Enum
Values		
	Auto	
	Manual	
InterFram	neTime	Double
Range	From 1e-009 to 10 step 1e-009	
MinSamp	lesPerBit	Integer
Range	From 4 to 100 step 1	
TDMChan	nnel	Integer
Range	From 1 to 8 step 1	
ViewingM	lode	Enum
Values		
	ASCII	
	Binary	
	Dec	
	Dec	

DECODEX

app.SerialDecode.Decodex

AnnotationPosition	Enum
DataSource	Enum

OutputFile	FileName
Protocol	Enum
View	Bool
ViewDecode	Bool

AnnotationPosition Enum

Values

Bottom	
Centered	
OnNoisyTrace	
OnTrace	
Тор	

DataSource Enum

Description

The Data Source has to be entered here. The source can be any channel, function or memory. The Data Source is required for every protocol supported whereas Clock and Chip Select might not be

Values

BadBits	
BadBits2	
Bits	
Bits2	
C1	
C2	
C3	
C4	
D0	
D1	
D10	
D11	
D12	
D13	
D15	
D16	
D17	
D18	
D19	
D2	
D20	
D21	
D22	
D23	
D24	
D25	
D26	
D27	
D28	
D29	
D3	
D30	
D31	
D32	
D33	
D34	
D35	
D4	
D5	

D6	
D7	
D8	
D9	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye	
Eye2	
F1	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
FLXEye	
Harm	
1	
M1	
M2	
M3	
M4	
Mod	
PointA	
PointB	
PointC	
PointD	
PointF	
PointH	
PRBS	
Pwr	
R	
ScanHisto	
ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	
V	
Z2	
Z3	
Z4	

Z5	
Z6	
Z7	
Z8	

OutputFile FileName

Range Any number of characters

Description

The name and path of the File used to export the Decoded Table

Protocol Enum

Description

The protocol currently decoded by this Decoder. At the time of this writing (July of 2007) we support 7 protocols:8b10, CAN, FlexRay, I2C, LIN, UART, SPI. The options purchased govern the list of visible protocol in this field.

Values

8B10B	
Audiol2S	
AudioLJ	
AudioRJ	
AudioTDM	
CAN	
CANHL	
FLX	
GMCANHL	
GMCANLAN	
I2C	
LIN	
MIL1553	
PCIE1X1	
PCIE1X2	
PCIE4X1	
RS232	
SIOP	
SPI	
SPICustom	
SPIDDR	
SSPI	
UART	
USART	

View Bool

Description

Turns the Table View on and off.

ViewDecode Bool

Description

Turns the Annotation View on and off.

DECODE

app.SerialDecode.Decodex.Decode

BitRate	Double
ColumnState	String
FilteredSymbolList	String
LevelPercent	Double
LevelType	Enum
PrimitiveFile	FileName
PrimitiveSource	Enum
ViewingMode	Enum

BitRate Double

Range From 1000 to 1e+010 step 0.0001

Description

The Bitrate of the data stream to be decoded

ColumnState String

Range Any number of characters

Description

This variable lists the visibility state of the columns in the decoded table Each column is named, followed by an equal sign and the state on or off. On turns on the column, off turns it off.

Example

The following command would show 3 columns
Time=on|Data=on|DataLength=on
whereas this comand would only show Time and DataLength
Time=on|Data=on|DataLength=off

FilteredSymbolList

String

Range Any number of characters

LevelPercent Double

Range From 0 to 100 step 0.1

Description

The threshold between zeros and ones expressed in Percent of the distance between top and base.

_evelTyp	е			Enum
Descrip	tion			
-		absolute and relative threshold mode		
Values				
Values	Absolute			7
	Percent			_
				」 - — - — - <u>— , — -</u> , — - —
Primitivel				FileName
Range	Any number of cl	haracters		
Primitives	Source			Enum
	Source			Liiuiii
Values				
	8b10b			1
	Others			-
	PCIE			_
	PCIE20			
	SAS			=
	SATA			
	USB3			
	XAUI			
/iewingN	lode			Enum
Descrip		usually historica Binary Have desired ACCII		
Sele	ects viewing mode,	usually between Binary,Hexadecimal, ASCII		
Values				
	Hexadecimal			7
	Symbolic			
				_
RESUL	_T	app.Se	rialDecode.Dec	odex.Out.Result
		DE ann	SerialDecode F	- FlexRayMeasure
	RAYMEASU	KE SP		
	AsymmetricDe	lou	Dool	
	Bitrate	nay	Bool	
	Channel		Enum	
	FrameTSSLen	gthChange	Bool	
	Jitter	gurvinango	Bool	
	NodeM		Enum	
	NodeN		Enum	
	ProbeOn		Enum	

PropagationDela	у	Bool
SIVoting		Bool

AsymmetricDelay		Bool
Bitrate		Double
Range	From 1000 to 1e+012 step 1000	
Channel		Enum
Values	s	
	A	
	В	
FrameTS	SSLengthChange	Вооі
Jitter		Воог
NodeM		Enum

Values

•	
C1	
C2	
C3	
C4	
F1	
F2	
F3	
F4	
M1	
M2	
M3	
M4	
Z1	
Z2	
Z3	
Z4	
Z5	
Z6	
Z 7	
Z8	

NodeN Enum

Values

C1	
C2	
C3	
C4	
F1	
F2	
F3	
F4	
M1	
M2	
M3	
M4	
Z1	
Z2	
Z3	
Z4	
Z5	
Z6	
Z7	
Z8	

ProbeOn Enum

Values

BPBM	
RXDTXD	

PropagationDelay Bool

SIVoting Bool

FLXEYE

app.SerialDecode.FLXEye

AxisXRotation	Integer
AxisYRotation	Integer
Bitrate	Double
Channel	Enum
ClearSweeps	Action
LabelsPosition	String
LabelsText	String
MaskTestOn	Bool
MaskType	Enum
Persist3DQuality	Enum

Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	
PersistenceTime	Enum
ShowLastTrace	Bool
Source	Enum
StopOnViolation	Bool
UseGrid	String
View	Bool
ViewLabels	Bool

AxisXRotation Integer From -90 to 90 step 1 Range **AxisYRotation** Integer From -90 to 90 step 1 Range Description This control is used only when Persisted is true and Persistence3d is true. It controls rotation about the Y axis of the view being persisted. **Bitrate** Double From 1000 to 1e+012 step 1000 Range Channel **Enum Values** Α В **ClearSweeps** Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

Labels Position String

Range Any number of characters

Description

Sets / Queries the horizontal position of the label attached to the acquisition trace Cx. The unit of measurement is the unit of the horizontal scale. The measurement is made from the trigger point. Note that this control is a string, not a numeric value. This allows multiple labels to be positioned, as shown in the example below.

LabelsText String

Range Any number of characters

Automation Command and Query Reference Manual - Control Reference			
MaskTes	tOn		Bool
MaskTyp	e		Enum
Values	5		
	bitrate10Mbps		
	bitrate2p5Mbps		
	bitrate5Mbps		
Persist3I	OQuality		Enum
Descrip	otion		
the be r if m	3D view is shown as monochrome or cold onochrome the bright with height. "Shade	effect when Persisted is true and Persistence3D is true. It controls whether is a wire frame (which can be monochrome or color graded), a solid (also can be graded), or a shaded solid (always monochrome). For WireFrame or Solid, intness increases with height; if color graded the color changes from puple to be greater the solid as if it were lit from the upper left.	
values	•		
	Shaded		
	Solid		
	WireFrame		
Persisted	 d		Bool
Descrip	otion		
Set: 'AIIL Dis _l	s/Queries the persis Locked' then the per	ted state of the waveform. If the Display.LockPersistence control is set to sisted state of all displayed waveforms will be the same. If the e control is set to 'PerTrace' then the persisted state of each waveform may be d.	
Persister	nce3d		Bool
Descrip	otion		
third sho cold poir	d dimension, to a pe wn as height above or or brightness as p nts with one or very f	re map from a two-dimensional surface with brightness or color indicating the respective rendering of a three dimensional object, where the third dimension is the surface formed by points which are not lit. In 3d, that surface is same oints with one or very few hits so that the surface is visible; but that means ew hits cannot be distinguished from the background. See also controls the appearance of the 3D object.	
Persister	nceMonoChrome		Bool
Descrip	otion		
Wh true	en this control is false, persistence is mor	se (the default state), persistence is color graded. When this control is set to nochrome, in the color of the trace, and increasing number of hits is shown as This control only has an effect when Persisted is true.	

PersistenceSaturation Integer

Range From 0 to 100 step 1

Description

Sets/Queries the saturation threshold for persisted waveforms.

All information at this level or above will be recorded with the same color or intensity.

See the general description above for a discussion of the locked and unlocked persistence modes.

PersistenceTime Enum

Description

Sets/Queries the state of the Persistence Time control. Controls the persistence decay time for this trace. See the general description above for a discussion of the locked and unlocked persistence modes.

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

ShowLastTrace Bool

Description

Sets/Queries the state of the Show Last Trace control. If True then when this trace is displayed in persistence mode the last acquired waveform will be superimposed on the accumulating persistence map.

See the general description above for a discussion of the locked and unlocked persistence modes.

Source	Enum
bource	Enam

Values

C1	
C2	
C3	
C4	
F1	
F2	
F3	
F4	
M1	
M2	
M3	
M4	
Z1	
Z 2	
Z3	
Z4	
Z 5	
Z6	
Z7	
Z8	

StopOnViolation Book

UseGrid String

Range Any number of characters

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

ViewLabels Book

Description

Sets/Queries whether the user-defined labels for the trace are visible. See Also: LabelsPosition and LabelsText controls.

RESULT

app.SerialDecode.FLXEye.Out.Result

MEASURE

app.SerialDecode.Measure

P1	Enum
P2	Enum
P3	Enum
P4	Enum
P5	Enum
P6	Enum
ViewCANParam	Bool

P1 Enum

Amalituda	
Amplitude	
CANLoad	
CANMsgBR	
CANMsgNum	
CANtoAnalog	
CANtoCAN	
CANtoValue	
Fall	
Fall8020	
FallAtLevel	
FullWidthAtHalfMaximum	
FullWidthAtXX	
HistogramBase	
HistogramMaximum	
HistogramMean	
HistogramMedian	
HistogramMid	
HistogramMinimum	
HistogramRms	
HistogramSdev	
HistogramTop	
MaximumPopulation	
Mode	
Null	
OvershootNegative	
OvershootPositive	
Peaks	
Percentile	
PopulationAtX	
Range	
Rise	
Rise2080	
RiseAtLevel	
TimeAtCAN	

TotalPopulation	
XAtPeak	

P2 Enum

·	
Amplitude	
CANLoad	
CANMsgBR	
CANMsgNum	
CANtoAnalog	
CANtoCAN	
CANtoValue	
Fall	
Fall8020	
FallAtLevel	
FullWidthAtHalfMaximum	
FullWidthAtXX	
HistogramBase	
HistogramMaximum	
HistogramMean	
HistogramMedian	
HistogramMid	
HistogramMinimum	
HistogramRms	
HistogramSdev	
HistogramTop	
MaximumPopulation	
Mode	
Null	
OvershootNegative	
OvershootPositive	
Peaks	
Percentile	
PopulationAtX	
Range	
Rise	
Rise2080	
RiseAtLevel	
TimeAtCAN	
TotalPopulation	
XAtPeak	

Р3 Enum

Amplitude	
CANLoad	
CANMsgBR	
CANMsgNum	
CANtoAnalog	
CANtoCAN	
CANtoValue	
Fall	
Fall8020	
FallAtLevel	
FullWidthAtHalfMaximum	
FullWidthAtXX	
HistogramBase	
HistogramMaximum	
HistogramMean	
HistogramMedian	
HistogramMid	
HistogramMinimum	
HistogramRms	
HistogramSdev	
HistogramTop	
MaximumPopulation	
Mode	
Null	
OvershootNegative	
OvershootPositive	
Peaks	
Percentile	
PopulationAtX	
Range	
Rise	
Rise2080	
RiseAtLevel	
TimeAtCAN	
TotalPopulation	
XAtPeak	
our	

P4 Enum

Amplitude	
CANLoad	
CANMsgBR	
CANMsgNum	
CANtoAnalog	
CANtoCAN	
CANtoValue	
Fall	
Fall8020	
FallAtLevel	
FullWidthAtHalfMaximum	
FullWidthAtXX	
HistogramBase	
HistogramMaximum	
HistogramMean	
HistogramMedian	
HistogramMid	
HistogramMinimum	
HistogramRms	
HistogramSdev	
HistogramTop	
MaximumPopulation	
Mode	
Null	
OvershootNegative	
OvershootPositive	
Peaks	
Percentile	
PopulationAtX	
Range	
Rise	
Rise2080	
RiseAtLevel	
TimeAtCAN	
TotalPopulation	
XAtPeak	

P5 Enum

Amplitude	
CANLoad	
CANMsgBR	
CANMsgNum	
CANtoAnalog	
CANtoCAN	
CANtoValue	
Fall	
Fall8020	
FallAtLevel	
FullWidthAtHalfMaximum	
FullWidthAtXX	
HistogramBase	
HistogramMaximum	
HistogramMean	
HistogramMedian	
HistogramMid	
HistogramMinimum	
HistogramRms	
HistogramSdev	
HistogramTop	
MaximumPopulation	
Mode	
Null	
OvershootNegative	
OvershootPositive	
Peaks	
Percentile	
PopulationAtX	
Range	
Rise	
Rise2080	
RiseAtLevel	
TimeAtCAN	
TotalPopulation	
XAtPeak	

P6 Enum

Values

Amplitude	
CANLoad	
CANMsgBR	
CANMsgNum	
CANtoAnalog	
CANtoCAN	
CANtoValue	
Fall	
Fall8020	
FallAtLevel	
FullWidthAtHalfMaximum	
FullWidthAtXX	
HistogramBase	
HistogramMaximum	
HistogramMean	
HistogramMedian	
HistogramMid	
HistogramMinimum	
HistogramRms	
HistogramSdev	
HistogramTop	
MaximumPopulation	
Mode	
Null	
OvershootNegative	
OvershootPositive	
Peaks	
Percentile	
PopulationAtX	
Range	
Rise	
Rise2080	
RiseAtLevel	
TimeAtCAN	
TotalPopulation	
XAtPeak	

ViewCANParam Bool

SPECANALYZER

app.SpecAnalyzer

ActualResolutionBandwidth	Double
AutoResolutionBandwidth	Bool

CenterFreq	Double
Enable	Bool
ENBW	Double
MarkerToCenterFreq	Action
MaxFrequency	Double
MaxPeaks	Integer
Mode	Enum
ReferenceFreq	Double
ReferenceLevel	Double
ResolutionBandwidth	DoubleLockstep
ShowPeakTable	Bool
Source	Enum
SpanFreq	Double
SpanMode	Enum
VerticalScale	DoubleLockstep
Window	Enum

ActualResolutionBandwidth

Double

Range From 0.1 to 1e+011 step 0.1

Description

Read-only control which reflects the current resolution bandwidth.

Note that this may differ from the ResolutionBandwidth control in cases where the user-requested resolution bandwidth cannot be achieved.

AutoResolutionBandwidth

Bool

Description

If set to TRUE, the resolution bandwidth will be automatically determined, based on 1/1000th of the frequency span requested.

CenterFreq Double

Range From 100 to 1e+010 step 100

Description

Spectrum center frequency.

Enable Bool

Description

Enable/Disable Spectrum Analyzer mode.

ENBW Double

Range From 0.1 to 10 step 0.001

Description

Readout of the current Equivalent Noise Bandwidth (ENBW).

MarkerToCenterFreq

Action

Description

Center the spectrum on the current market frequency.

MaxFrequency

Double

Range From 100000 to 1e+011 step 1

Description

Read-only control, reflects the maximum frequency of the spectrum. Calculated as 1/2 the scope sample rate.

MaxPeaks

Integer

Range From 1 to 100 step 1

Description

Define the maximum number of peaks which will be measured, and presented in the table.

Mode

Enum

Description

Define the spectrum analyzer mode.

Values

Average	Average a number of traces, specified in the NumAverages control.
MaxHold	Record the maximum value in each frequency bin.
Normal	Normal Mode.

ReferenceFreq Double

Range From 0 to 1e+010 step 1

Description

Defines the reference frequency, at which point a vertical marker (cursor) will be displayed.

ReferenceLevel Double

Range From -200 to 200 step 0.0001

Description

Define the vertical reference level, that is the level in dBm, that is shown at the top of the graticule.

ResolutionBandwidth

DoubleLockstep

Range From 0.1 to 1e+009 step 1000, locked to 1 3 5, fine grain allowed=false, on=false

Description

When not in Auto Resolution Bandwidth mode, this control is used to request a specific resolution bandwidth.

Note that the requested resolution bandwidth is not always achieveable, so a second control, ActualResolutionBandwidth is available to verify that the actual resolution bandwidth is acceptable.

ShowPea	ıkTable		Bool
Descrip If TF plot.	RUE, the table of det	tected peaks, and their respective amplitudes, is shown beside the spectra	I
Source			Enum
		. Note that only acquisition channels may be used as sources to the spectr	um
Values	;		
	C1		
	C2		
	C3		
	C4		
SpanFred			Double
-	From 100 to 1e+0	110 stop 100	
Range	1101111001016+0	TO Step 100	
Descrip Defi		ncy, valid when the SpanMode control is in CenterSpan mode.	
SpanMod	le		Enum
	ne the way in which uency, or as a Start	the span of the spectrum is controlled, either as a Center and Span and Stop frequency.	
values			
	CenterAndSpan		
	StartAndStop		
VerticalS	cale	Dou	bleLockstep
Range	From 0.1 to 100 s	tep 0.2, locked to 1 2 5, fine grain allowed=false, on=false	
Descrip Defi		of the spectrum, in units of dB.	
Window			Enum
Descrip Defi		ion used to compute the FFT of the input signal.	
Values	;		
	BlackmanHarris		
	FlatTop		
	Hamming		
	VonHann		

AxisXRotation	Integer
AxisYRotation	Integer
ClearSweeps	Action
LabelsPosition	String
LabelsText	String
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ShowLastTrace	Bool
UseGrid	String
View	Bool
ViewLabels	Bool

AxisXRotation Integer

Range From -90 to 90 step 1

AxisYRotation Integer

Range From -90 to 90 step 1

Description

This control is used only when Persisted is true and Persistence3d is true. It controls rotation about the Y axis of the view being persisted.

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

Labels Position String

Range Any number of characters

Description

Sets / Queries the horizontal position of the label attached to the acquisition trace Cx. The unit of measurement is the unit of the horizontal scale. The measurement is made from the trigger point. Note that this control is a string, not a numeric value. This allows multiple labels to be positioned, as shown in the example below.

LabelsText String

Range Any number of characters

Persist3DQuality Enum

Description

This control only has an effect when Persisted is true and Persistence3D is true. It controls whether the 3D view is shown as a wire frame (which can be monochrome or color graded), a solid (also can be monochrome or color graded), or a shaded solid (always monochrome). For WireFrame or Solid, if monochrome the brightness increases with height; if color graded the color changes from puple to red with height. "Shaded" present the solid as if it were lit from the upper left.

Values

Shaded	
Solid	
WireFrame	

Persisted Bool

Description

Sets/Queries the persisted state of the waveform. If the Display.LockPersistence control is set to 'AllLocked' then the persisted state of all displayed waveforms will be the same. If the Display.LockPersistence control is set to 'PerTrace' then the persisted state of each waveform may be independently controlled.

Persistence3d Bool

Description

Changes the persistence map from a two-dimensional surface with brightness or color indicating the third dimension, to a perspective rendering of a three dimensional object, where the third dimension is shown as height above the surface formed by points which are not lit. In 3d, that surface is same color or brightness as points with one or very few hits so that the surface is visible; but that means points with one or very few hits cannot be distinguished from the background. See also Persist3DQuality, which controls the appearance of the 3D object.

PersistenceMonoChrome

Bool

Description

When this control is false (the default state), persistence is color graded. When this control is set to true, persistence is monochrome, in the color of the trace, and increasing number of hits is shown as increasing brightness. This control only has an effect when Persisted is true.

PersistenceSaturation

Integer

Range From 0 to 100 step 1

Description

Sets/Queries the saturation threshold for persisted waveforms.

All information at this level or above will be recorded with the same color or intensity.

See the general description above for a discussion of the locked and unlocked persistence modes.

PersistenceTime Enum

Description

Sets/Queries the state of the Persistence Time control. Controls the persistence decay time for this trace. See the general description above for a discussion of the locked and unlocked persistence modes.

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

ShowLastTrace Bool

Description

Sets/Queries the state of the Show Last Trace control. If True then when this trace is displayed in persistence mode the last acquired waveform will be superimposed on the accumulating persistence map.

See the general description above for a discussion of the locked and unlocked persistence modes.

UseGrid String

Range Any number of characters

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

ViewLabels Book

Description

Sets/Queries whether the user-defined labels for the trace are visible.

See Also: LabelsPosition and LabelsText controls.

RESULT

app.SpecAnalyzer.SpecAn.Out.Result

SPECANTABLE

app.SpecAnalyzer.SpecAnTable

ClearSweeps	Action
TableLocation	String
View	Bool

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

TableLocation String

Range Any number of characters

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.SpecAnalyzer.SpecAnTable.Out.Result

SYSTEMCONTROL

app.SystemControl

FrontPanelEventTimestamp	String
ModalDialogTimeout	Integer
PersistentMessage	String

FrontPanelEventTimestamp

String

Range Any number of characters

ModalDialogTimeout

Integer

Range From 0 to 120 step 1

Description

Set a timeout, in units of seconds, used to auto-dismiss modal dialogs, with their default responses.

PersistentMessage

String

Range Any number of characters

DATETIMESETUP

app.Utility.DateTimeSetup

This set of variables controls user the date and time setup. In addition to manual controls for hh/mm/ss, dd/mm/yy, there is the ability to set the time and date from an Internet clock using the SNTP protocol.

CurrentDateAndTime	String
Day	Integer
Hour	Integer
Minute	Integer

Month	Integer
Second	Integer
SetFromSNTP	Action
Validate	Action
Year	Integer

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Set time/date from the NIST Internet clock app.Utility.DateTimeSetup.SetFromSNTP

CurrentDateAndTime String

Range Any number of characters

Description

Reads the current date and time from the real-time calendar and clock.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

 $^{\prime}$ Read the current date and time from the real-time calendar and clock. app.Utility.DateTimeSetup.CurrentDateAndTime

Day Integer

Range From 1 to 31 step 1

Description

Sets/Queries the day of the month setting of the real-time clock as a number. The value will not be accepted by the clock until app.Utility.DateTimeSetup.Validate is sent. All time/date controls are validated at the same time.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the day of the month as 21.
app.Utility.DateTimeSetup.Day = 21
app.Utility.DateTimeSetup.Validate
```

Hour Integer

Range From 0 to 23 step 1

Description

Sets/Queries the hours setting of the real-time clock as a number. The value will not be accepted by the clock until app.Utility.DateTimeSetup.Validate is sent. All time/date controls are validated at the same time.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the hour as 13.
app.Utility.DateTimeSetup.Hour = 13
app.Utility.DateTimeSetup.Validate
```

Minute Integer

Range From 0 to 59 step 1

Description

Sets/Queries the minutes setting of the real-time clock as a number. The value will not be accepted by the clock until app.Utility.DateTimeSetup.Validate is sent. All time/date controls are validated at the same time.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the minute as 34.
app.Utility.DateTimeSetup.Minute = 34
app.Utility.DateTimeSetup.Validate
```

Month Integer

Range From 1 to 12 step 1

Description

Sets/Queries the month setting of the real-time clock as a number. The value will not be accepted by the clock until app.Utility.DateTimeSetup.Validate is sent. All time/date controls are validated at the same time.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the month as August.
app.Utility.DateTimeSetup.Month = 8
app.Utility.DateTimeSetup.Validate
```

Second Integer

Range From 0 to 59 step 1

Description

Sets/Queries the seconds setting of the real-time clock as a number. The value will not be accepted by the clock until app.Utility.DateTimeSetup.Validate is sent. All time/date controls are validated at the same time.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the seconds as 55.
app.Utility.DateTimeSetup.Second = 55
app.Utility.DateTimeSetup.Validate
```

SetFromSNTP Action

Description

Sets the real time clock from the simple network time protocol.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the real time clock from the simple network time protocol.
app.Utility.DateTimeSetup.SetFromSNTP
```

Validate Action

Description

Validates any new settings. This action is equivalent to clicking 'Validate Changes' on the Date/Time page.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the day, hour, and minute, and validate.
app.Utility.DateTimeSetup.Day = 3
app.Utility.DateTimeSetup.Hour = 5
app.Utility.DateTimeSetup.Minute = 8
app.Utility.DateTimeSetup.Validate
```

Year Integer

From 2000 to 2037 step 1 Range

Description

Sets/Queries the year setting of the real-time clock as a number. The value will not be accepted by the clock until app.Utility.DateTimeSetup.Validate is sent. All time/date controls are validated at the same time.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCrov.XStreamDSO")
' Set the year as 2003.
app.Utility.DateTimeSetup.Year = 2003
app.Utility.DateTimeSetup.Validate
```

app.Utility.Options **OPTIONS**

Options subsystem, contains controls to query the list of installed software and hardware options.

InstalledHWOptions	String
InstalledSWOptions	String
ScopeID	String

InstalledHWOptions String

Any number of characters Range

Description

Shows a list of the installed hardware options.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Read the list of installed hardware options and present
' in a popup dialog
MsgBox app. Utility. Options. Installed HWOPtions
```

Any number of characters

String

Description

InstalledSWOptions

Shows list of installed software options.

Example

Range

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Read the list of installed software options and display
' in a popup dialog
MsgBox app. Utility. Options. Installed SWOPtions
```

ScopeID String

Range Any number of characters

Description

Queries the ID of the instrument. This ID should be specified when purchasing software options for your instrument.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Read the ID of the instrument.
MsgBox app.Utility.Options.ScopeID
```

REMOTE app.Utility.Remote

Controls related to the remote control section of the instrument. Note that in this context Automation is not considered part of 'Remote'. Remote control currently includes control using ASCII remote commands from GPIB or TCP/IP.

Assistant	Enum
Interface	Enum
RestrictControl	Enum
SetToErrorsOnlyAndClearAtStartup	Bool

Assistant Enum

Description

Sets/Queries the setting of the remote assistant.

Values

EO	Log errors only
FD	Log all remote commands/queries
OFF	Turn the assistant off

Interface Enum

Description

Sets/Queries the currently selected type of currently selected remote control interface.

LXI	
Off	
TCPIP	

Enum

Description

Sets/Queries whether remote control is restricted to certain hosts, where the host name is defined either by IP address, or dns name.

Values

No	
Yes	

SetToErrorsOnlyAndClearAtStartup

Bool

Description

Enable the resetting of the remote assistant to 'Errors Only' mode when the instrument is reset. Also ensure s that the remote assistant log is cleared upon startup.

This control is set by default to lower the risk that the remote assistant will be set to 'Full Dialog' mode and be forgotten, causing a decrease in remote control performance.

CIOPORTU3GPIB

app.Utility.Remote.IOManager.CIOPortU3GPIB

GpibAddress	Integer

GpibAddress Integer

Range From 1 to 30 step 1

CLSIBPORT

app.Utility.Remote.IOManager.CLSIBPort

WAVESCAN app. WaveScan

This is the root of the WaveScan automation hierarchy.

WaveScan enables you to search for unusual events in a single capture, or to scan for an event in many acquisitions over a long period of time.

It may be considered a kind of software trigger.

Enable	Bool
FindRare1Sigma	Action
FindRare3Sigma	Action
FindRare5Sigma	Action
FindUseMean	Action
ShowTimes	Bool

Enable Bool

Description

Sets/Queries the WaveScan enabled state.

FindRare1Sigma

Action

Description

Preset the filter limit and delta to find rare events. Uses the history of measurements since the last Clear Sweeps, or control change, to set the limit and delta to capture +/- 1 sigma events.

FindRare3Sigma

Action

Description

Preset the filter limit and delta to find rare events. Uses the history of measurements since the last Clear Sweeps, or control change, to set the limit and delta to capture +/- 3 sigma events.

FindRare5Sigma

Action

Description

Preset the filter limit and delta to find rare events. Uses the history of measurements since the last Clear Sweeps, or control change, to set the limit and delta to capture +/- 5 sigma events.

FindUseMean

Action

Description

Setup the filter to find measurements with values > the current statistical mean.

ShowTimes

Bool

SCANDECODE

app.WaveScan.ScanDecode

ClearSweeps	Action
TableLocation	String
View	Bool

ClearSweeps

Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

TableLocation

String

Range

Any number of characters

Description

View

Bool

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.WaveScan.ScanDecode.Out.Result

SCANHISTO

app.WaveScan.ScanHisto

AxisXRotation	Integer
AxisYRotation	Integer
ClearSweeps	Action
LabelsPosition	String
LabelsText	String
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ShowLastTrace	Bool
View	Bool
ViewLabels	Bool

AxisXRotation Integer

Range From -90 to 90 step 1

AxisYRotation Integer

Range From -90 to 90 step 1

Description

This control is used only when Persisted is true and Persistence3d is true. It controls rotation about the Y axis of the view being persisted.

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

LabelsPosition String

Range Any number of characters

Description

Sets / Queries the horizontal position of the label attached to the acquisition trace Cx. The unit of measurement is the unit of the horizontal scale. The measurement is made from the trigger point. Note that this control is a string, not a numeric value. This allows multiple labels to be positioned, as shown in the example below.

LabelsText String

Range Any number of characters

Persist3DQuality Enum

Description

This control only has an effect when Persisted is true and Persistence3D is true. It controls whether the 3D view is shown as a wire frame (which can be monochrome or color graded), a solid (also can be monochrome or color graded), or a shaded solid (always monochrome). For WireFrame or Solid, if monochrome the brightness increases with height; if color graded the color changes from puple to red with height. "Shaded" present the solid as if it were lit from the upper left.

Values

Shaded	
Solid	
WireFrame	

Persisted Bool

Description

Sets/Queries the persisted state of the waveform. If the Display.LockPersistence control is set to 'AllLocked' then the persisted state of all displayed waveforms will be the same. If the Display.LockPersistence control is set to 'PerTrace' then the persisted state of each waveform may be independently controlled.

Persistence3d Bool

Description

Changes the persistence map from a two-dimensional surface with brightness or color indicating the third dimension, to a perspective rendering of a three dimensional object, where the third dimension is shown as height above the surface formed by points which are not lit. In 3d, that surface is same color or brightness as points with one or very few hits so that the surface is visible; but that means points with one or very few hits cannot be distinguished from the background. See also Persist3DQuality, which controls the appearance of the 3D object.

PersistenceMonoChrome

Bool

Description

When this control is false (the default state), persistence is color graded. When this control is set to true, persistence is monochrome, in the color of the trace, and increasing number of hits is shown as increasing brightness. This control only has an effect when Persisted is true.

PersistenceSaturation

Integer

Range From 0 to 100 step 1

Description

Sets/Queries the saturation threshold for persisted waveforms.

All information at this level or above will be recorded with the same color or intensity.

See the general description above for a discussion of the locked and unlocked persistence modes.

PersistenceTime Enum

Description

Sets/Queries the state of the Persistence Time control. Controls the persistence decay time for this trace. See the general description above for a discussion of the locked and unlocked persistence modes.

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

ShowLastTrace Bool

Description

Sets/Queries the state of the Show Last Trace control. If True then when this trace is displayed in persistence mode the last acquired waveform will be superimposed on the accumulating persistence map.

See the general description above for a discussion of the locked and unlocked persistence modes.

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

ViewLabels Bool

Description

Sets/Queries whether the user-defined labels for the trace are visible.

See Also: LabelsPosition and LabelsText controls.

HISTOGRAM

app.WaveScan.ScanHisto.Histogram

AutoFindScale	Bool
Bins	DoubleLockstep
BufferSize	Integer
Center	Double
ClearSweeps	Action
FindScale	Action
HorScale	DoubleLockstep
Values	Integer
VerScaleType	Enum

AutoFindScale Bool

Description

Defines whether the histogram horizontal axis is automatically scaled when sufficient data has been accumulated.

The FindScale control may be used to manually find the scale, if this control is set to False.

Bins

DoubleLockstep

Range From 20 to 2000 step 1, locked to 1 2 5, fine grain allowed=false, on=false

Description

Number of bins in the histogram.

BufferSize

Integer

Range From 200 to 5000 step 1

Description

Size of the buffer which stores incoming parameter values, ready to be histogrammed. Not to be confused with the 'Values' control, which defines the number of values from the buffer which are currently rendered in the histogram.

Center

Double

Range From -1e+010 to 1e+010 step 1e-012

Description

Defines the value of the bin which is centered horizontally within the graticule.

ClearSweeps

Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

FindScale

Action

Description

Automatically determine an appropriate horizontal scale for the histogram, using the values currently in the histogram buffer.

HorScale

DoubleLockstep

Range From 1e-012 to 1e+012 step 0.01, locked to 1 2 5, fine grain allowed=false, on=false

Description

Horizontal scale of the histogram, per division of the graticule.

Values

Integer

Range From 20 to 2000000000 step 1

Description

Size of the buffer in which all values currently histogrammed are queued.

VerScaleType	Enu.	m

Description

Vertical Scale mode of the histogram, Linear, or 'Linear with Constant Maximum'.

Values

LinConstMax	
Linear	

RESULT

app.WaveScan.ScanHisto.Out.Result

ZOOM

app.WaveScan.ScanHisto.Zoom

HorPos	Double
HorZoom	Double
ResetZoom	Action
VariableHorZoom	Bool
VariableVerZoom	Bool
VerPos	Double
VerZoom	Double

HorPos Double

Range From -0.5 to 0.5 step (8 digits)

Description

Horizontal Position of the trace, normalized to a value between -0.5 and 0.5. A value of zero is the default, and indicates no position change relative to the source trace.

HorZoom Double

Range From 0.1 to 1e+006 step (8 digits)

Description

Horizontal Zoom setting. Locked to a 1, 2, 5 sequence unless VariableHorZoom is set to True.

ResetZoom Action

Description

Resets the zoom settings to their default values.

VariableHorZoom Bool

Description

Enable/Disable the variable Horizontal Zoom control. If enabled, the HorZoom control may be set to a value other than the standard 1, 2, 5 sequence.

VariableVerZoom Bool

Description

Enable/Disable the variable Vertical Zoom control. If enabled, the VerZoom control may be set to a value other than the standard 1, 2, 5 sequence.

VerPos Double

Range From -1.5 to 1.5 step (8 digits)

Description

Vertical Position of the trace, normalized to a value between -1.5 and 1.5. A value of zero is the default, and indicates no position change relative to the source trace.

VerZoom Double

Range From 0.1 to 100 step (8 digits)

Description

Vertical Zoom setting. Locked to a 1, 2, 5 sequence unless VariableVerZoom is set to True .

SCANOVERLAY

app.WaveScan.ScanOverlay

AxisXRotation	Integer
AxisYRotation	Integer
ClearSweeps	Action
EnablePersistence	Bool
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ShowLastTrace	Bool
View	Bool

AxisXRotation Integer

Range From -90 to 90 step 1

AxisYRotation Integer

Range From -90 to 90 step 1

Description

This control is used only when Persisted is true and Persistence3d is true. It controls rotation about the Y axis of the view being persisted.

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

EnablePersistence Bool

Description

Set to place the WaveScan 'ScanOverlay' in persistence mode, as opposed to 'overlay' mode (where all contributing sub-waveforms are overlaid)

Persist3DQuality Enum

Description

This control only has an effect when Persisted is true and Persistence3D is true. It controls whether the 3D view is shown as a wire frame (which can be monochrome or color graded), a solid (also can be monochrome or color graded), or a shaded solid (always monochrome). For WireFrame or Solid, if monochrome the brightness increases with height; if color graded the color changes from puple to red with height. "Shaded" present the solid as if it were lit from the upper left.

Values

Shaded	
Solid	
WireFrame	

Persisted Bool

Description

Sets/Queries the persisted state of the waveform. If the Display.LockPersistence control is set to 'AllLocked' then the persisted state of all displayed waveforms will be the same. If the Display.LockPersistence control is set to 'PerTrace' then the persisted state of each waveform may be independently controlled.

Persistence3d Bool

Description

Changes the persistence map from a two-dimensional surface with brightness or color indicating the third dimension, to a perspective rendering of a three dimensional object, where the third dimension is shown as height above the surface formed by points which are not lit. In 3d, that surface is same color or brightness as points with one or very few hits so that the surface is visible; but that means points with one or very few hits cannot be distinguished from the background. See also Persist3DQuality, which controls the appearance of the 3D object.

PersistenceMonoChrome

Bool

Description

When this control is false (the default state), persistence is color graded. When this control is set to true, persistence is monochrome, in the color of the trace, and increasing number of hits is shown as increasing brightness. This control only has an effect when Persisted is true.

PersistenceSaturation

Integer

Range From 0 to 100 step 1

Description

Sets/Queries the saturation threshold for persisted waveforms.

All information at this level or above will be recorded with the same color or intensity.

See the general description above for a discussion of the locked and unlocked persistence modes.

PersistenceTime Enum

Description

Sets/Queries the state of the Persistence Time control. Controls the persistence decay time for this trace. See the general description above for a discussion of the locked and unlocked persistence modes.

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

ShowLastTrace Bool

Description

Sets/Queries the state of the Show Last Trace control. If True then when this trace is displayed in persistence mode the last acquired waveform will be superimposed on the accumulating persistence map.

See the general description above for a discussion of the locked and unlocked persistence modes.

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

RESULT

app.WaveScan.ScanOverlay.Out.Result

WEBEDITOR app.WebEditor

This set of variables controls the web-editor which show the paths for data flow in the instrument. This feature is not supported on all instruments. Currently it is supported on DDA and SDA models, and models with XMAP and/or XMATH software options.

AddConnection([in] VARIANT destProcessor, [in] VARIANT destInputPin, [in] VA	Method
AddPreview([in] VARIANT sourceProcessor, [in] VARIANT sourcePin, [in] BSTR	Method
AddProcessor([in] VARIANT processorOrClassId, [in] BSTR requestedName, [in]	Method
ClearSweeps	Action
GetProcessor([in] VARIANT processor)	Method
RemoveAlI()	Method
RemoveConnection([in] VARIANT destProcessor, [in] VARIANT destInputPin)	Method
RemovePreview([in] VARIANT processor)	Method
RemoveProcessor([in] VARIANT processor)	Method

Example

' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Enter auto-trigger mode
app.Acquisition.TriggerMode = "Auto"
' Show the web editor and remove all processors from it
app.ActiveView = "WebEdit"
app.WebEditor.RemoveAll
' Crea

AddConnection([in] VARIANT destProcessor, [in] VARIANT destInputPin, [in] VARIANT sourceProcessor, [in] VARIANT sourceOutputPin)

Method

Description

Add a connection between two 'pins' of nodes placed within the Web Editor.

Pins are described by the name of the node, and the zero-based index of the pin on that node.

AddPreview([in] VARIANT sourceProcessor, [in] VARIANT sourcePin, [in] BSTR previewName, [in] double xPosition, [in] double yPosition, [in] BSTR associatedExecName)

Method

Description

Add a Preview to the specified pin of the specified node. The coordinates specify where the preview will appear on the Web, with 0,0 being the top left-hand corner.

AddProcessor([in] VARIANT processorOrClassId, [in] BSTR requestedName, [in] double xPosition, [in] double yPosition)

Method

Description

Add a named 'processor' to the web. To determine the name of a processor just place it on the web using the GUI and hover the mouse over the node. The 'ProgID' of the node, in the format 'LeCroy.cprocName' will appear. Note that when adding processors from automation there is no distinction between Measure, Math, and Pass/Fail processors.

ClearSweeps Action

Description

Clear any accumulated data for nodes such as Average, Persistence, etc. that reside in the processing web.

GetProcessor([in] VARIANT processor)

Method

Description

Retrieve a reference to a processor that has been added to the Web. This reference may then be used to access the processor's controls. See the Math/Measure control reference section of this manual for a list of the available controls for each processor.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

```
' Show the web editor and remove all processors from it app.ActiveView = "WebEdit" app.WebEditor.RemoveAll
```

```
' Create a Waveform Averager, name it "MyAvg", and place it at x=200, y=30 app.WebEditor.AddProcessor "LeCroy.Average", "MyAvg", 200, 30
```

```
' Retrieve a pointer to the averager and set it's number of sweeps ' to the value 1234 set myAverager = app.WebEditor.GetProcessor("MyAvg") myAverager.Sweeps = 1234
```

RemoveAlI() Method

Description

Remove all processors from the web.

RemoveConnection([in] VARIANT destProcessor, [in] VARIANT destInputPin)

Method

Description

Remove a connection between two pins on the web.

RemovePreview([in] VARIANT processor)

Method

Description

Remove the named preview display.

RemoveProcessor([in] VARIANT processor)

Method

Description

Remove the named processor from the Web.

XPORT app.XPort

ZOOM app.Zoom

ConnectedToSuperKnob	Bool
GoToEnd	Action
GoToStart	Action
HorZoomIn	Action
HorZoomOut	Action

MultiZoomOn	Bool
QuickZoom	Action
ResetAll	Action
ResetZoom	Action
VariableHorZoom	Bool

ConnectedToSuperKnob	Bool
GoToEnd	Action
Description When in multi-zoom mode, scroll to the end of the source waveform, who's last point will be centered on the graticule.	
GoToStart	Action
Description When in multi-zoom mode, scroll to the start of the source waveform, who's first point will be centered on the graticule.	
HorZoomIn	Action
Description Horizontally zoom in all the traces included in MultiZoom.	
HorZoomOut	Action
Description Horizontally zoom out all the traces included in MultiZoom.	
MultiZoomOn	Bool
Description Turn MultiZoom On and includes all the Zx automatically if any viewed.	
QuickZoom	Action
Description Zoom all Cx that are on at an horizontal factor of 10.	
ResetAll	Action
Description Reset all Zx to their default settings.	
ResetZoom	Action
Description Resets the zoom settings to their default values.	
VariableHorZoom	Bool

Description

Enable/Disable the variable Horizontal Zoom control. If enabled, the HorZoom control may be set to a value other than the standard 1, 2, 5 sequence.

ZX app.Zoom.Zx

AxisXRotation	Integer
AxisYRotation	Integer
ClearSweeps	Action
DoStoreToMemoryTrace	Action
Equation	String
LabelsPosition	String
LabelsText	String
Persist3DQuality	Enum
Persisted	Bool
Persistence3d	Bool
PersistenceMonoChrome	Bool
PersistenceSaturation	Integer
PersistenceTime	Enum
ShowLastTrace	Bool
Source	Enum
UseGrid	String
View	Bool
ViewLabels	Bool

AxisXRotation Integer

Range From -90 to 90 step 1

AxisYRotation Integer

Range From -90 to 90 step 1

Description

This control is used only when Persisted is true and Persistence3d is true. It controls rotation about the Y axis of the view being persisted.

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

Action

Description

Store the content of Zx into the corresponding Memory Slot (Mx).

Equation String

Range Any number of characters

Description

Same as app.Math.Fx.Equation.

Labels Position String

Range Any number of characters

Description

Sets / Queries the horizontal position of the label attached to the acquisition trace Cx. The unit of measurement is the unit of the horizontal scale. The measurement is made from the trigger point. Note that this control is a string, not a numeric value. This allows multiple labels to be positioned, as shown in the example below.

LabelsText String

Range Any number of characters

Persist3DQuality Enum

Description

This control only has an effect when Persisted is true and Persistence3D is true. It controls whether the 3D view is shown as a wire frame (which can be monochrome or color graded), a solid (also can be monochrome or color graded), or a shaded solid (always monochrome). For WireFrame or Solid, if monochrome the brightness increases with height; if color graded the color changes from puple to red with height. "Shaded" present the solid as if it were lit from the upper left.

Values

Shaded	
Solid	
WireFrame	

Persisted Bool

Description

Sets/Queries the persisted state of the waveform. If the Display.LockPersistence control is set to 'AllLocked' then the persisted state of all displayed waveforms will be the same. If the Display.LockPersistence control is set to 'PerTrace' then the persisted state of each waveform may be independently controlled.

Persistence3d Bool

Description

Changes the persistence map from a two-dimensional surface with brightness or color indicating the third dimension, to a perspective rendering of a three dimensional object, where the third dimension is shown as height above the surface formed by points which are not lit. In 3d, that surface is same color or brightness as points with one or very few hits so that the surface is visible; but that means points with one or very few hits cannot be distinguished from the background. See also Persist3DQuality, which controls the appearance of the 3D object.

PersistenceMonoChrome

Bool

Description

When this control is false (the default state), persistence is color graded. When this control is set to true, persistence is monochrome, in the color of the trace, and increasing number of hits is shown as increasing brightness. This control only has an effect when Persisted is true.

PersistenceSaturation Integer

Range From 0 to 100 step 1

Description

Sets/Queries the saturation threshold for persisted waveforms.

All information at this level or above will be recorded with the same color or intensity.

See the general description above for a discussion of the locked and unlocked persistence modes.

PersistenceTime Enum

Description

Sets/Queries the state of the Persistence Time control. Controls the persistence decay time for this trace. See the general description above for a discussion of the locked and unlocked persistence modes.

Values

0.5s	
10s	
1s	
20s	
2s	
5s	
Infinite	

ShowLastTrace Bool

Description

Sets/Queries the state of the Show Last Trace control. If True then when this trace is displayed in persistence mode the last acquired waveform will be superimposed on the accumulating persistence map.

See the general description above for a discussion of the locked and unlocked persistence modes.

Source Enum

Description

Zoom source trace.

BadBits	
BadBits2	
Bits	
Bits2	
C1	
C2	
C3	
C4	
Digital1	
Digital2	
Digital3	
Digital4	
dvdt	
E100Dta	
E10Dta	
EnetDta	
ET	
Eye	
Eye2	
F1	
F2	
F3	
F4	
FiltData	
FiltJit	
FiltSlv	
FLXEye	
Harm	
I	
M1	
M2	
M3	
M4	
Mod	
PointA	
PointB	
PointC	
PointD	
PointF	
PointH	
PRBS	
_	

Pwr	
R	
ScanHisto	
ScanOverlay	
SigQual	
SineRemovedData	
SlvDtaJit	
SpecAn	
V	
Z2	
Z3	
Z4	
Z5	
Z6	
Z7	
Z8	

UseGrid String

Range Any number of characters

Description

Sets/Queries the grid in use for the zoom trace Zx. See also app.Acquisition.Cx.UseGrid.

View Bool

Description

Sets/Queries the trace's 'Viewed' state. When true, the trace is displayed on one of the display graticules. Note that even when a trace is not visible, it may be used as a source for Math, Measure, etc.

ViewLabels Bool

Description

Sets/Queries whether the user-defined labels for the trace are visible. See Also: LabelsPosition and LabelsText controls.

RESULT

app.Zoom.Zx.Out.Result

ZOOM

app.Zoom.Zx.Zoom

CenterSelectedSegment	Integer
HorPos	Double
HorZoom	Double
NumSelectedSegments	DoubleLockstep
VariableHorZoom	Bool

VariableVerZoom	Bool
VerPos	Double
VerZoom	Double

CenterSelectedSegment

Integer

Range From 1 to 1 step 1

HorPos

Double

Range From -0.5 to 0.5 step (8 digits)

Description

Horizontal Position of the trace, normalized to a value between -0.5 and 0.5. A value of zero is the default, and indicates no position change relative to the source trace.

HorZoom

Double

Range From 0.1 to 1e+006 step (8 digits)

Description

Horizontal Zoom setting. Locked to a 1, 2, 5 sequence unless VariableHorZoom is set to True.

NumSelectedSegments

DoubleLockstep

Range From 1 to 1 step 1, locked to 1 2 5, fine grain allowed=true, on=false

VariableHorZoom

Bool

Description

Enable/Disable the variable Horizontal Zoom control. If enabled, the HorZoom control may be set to a value other than the standard 1, 2, 5 sequence.

VariableVerZoom

Bool

Description

Enable/Disable the variable Vertical Zoom control. If enabled, the VerZoom control may be set to a value other than the standard 1, 2, 5 sequence.

VerPos

Double

Range From -1.5 to 1.5 step (8 digits)

Description

Vertical Position of the trace, normalized to a value between -1.5 and 1.5. A value of zero is the default, and indicates no position change relative to the source trace.

VerZoom

Double

Range From 0.1 to 100 step (8 digits)

Description

Vertical Zoom setting. Locked to a 1, 2, 5 sequence unless VariableVerZoom is set to True .

Mean	2-89
Median	2-89
Minimum	2-90
NarrowBandPhase	2-90
NCycleJitter	2-90
NonLinearTransitionShift	2-91
npoints	2-91
OvershootNegative	2-91
OvershootPositive	2-91
Overwrite	2-92
ParamScript	2-92
PEAKMAG	2-92
PeakToPeak	2-92
Percentile	2-93
PeriodAtLevel	2-93
Phase	2-94
Protocol2Analog	2-97
Protocol2Protocol	2-100
Protocol2Value	2-103
ProtocolBitrate	2-104
ProtocolLoad	2-106
ProtocolNumMessages	2-107
PW50	2-109
PW50Negative	2-109
PW50Positive	2-110
Resolution	2-110
RiseAtLevel	2-110
RootMeanSquare	2-111
Setup	2-111
Skew	2-113
Slew	2-116
StandardDeviation	2-117
TAA	2-117
TAANegative	2-117
TAAPositive	2-117
TIE	2-118
Time A+C ANI	2 422

TimeAtLevel	2-123
TimeAtProtocol	2-124
Тор	2-126
WidthAtLevel	2-126
XAtMaximum	2-127
XAtMinimum	2-127
XAtPeak	2-128
Average	2-1
Boxcar	2-2
Сору	2-2
Correlation	2-3
Demodulate	2-3
Derivative	2-4
Deskew	2-5
EnhancedResolution	2-5
Envelope	2-6
ExcelMath	2-6
FastWavePort	2-11
FFT	2-11
Filter	2-13
Floor	2-15
Histogram	
Htie2BER	
Integral	2-18
Interpolate	2-19
ISIPatt	
LowPassIIR	
MathcadMath	
MATLABWaveform	2-26
PersistenceHistogram	
PersistenceTraceMean	
PersistenceTraceRange	
PersistenceTraceSigma	
Reframe	
Rescale	
Roof	
SagmentSelect	2-31

SeqBuilder	
SequenceAverage	
SinXOverX	
Sparse	
Trend	
WaveScript	
MathcadParamArith	
ParamConst	
ParamInvert	
ParamMinMax	
ParamPassThru	
ParamRescale	
ParamScript	
Plimiter	
100BTfall	
100BTrise	
100BTTIE	
100BTTj	
10BTJ	
Amplitude	
AmplitudeAsymmetry	
Analog2Protocol	
Area	
AutoCorrelationSignalToNoise	
Base	
BurstWidth	
CANLoad	
CANMsgBR	
CANMsgNum	
CANtoAnalog	
CANtoCAN	
CANtoValue	
DeltaMessages	
DeltaPeriodAtLevel	
DeltaTimeAtLevel	
DeltaWidthAtLevel	
DOV	

DutyAtLevel	
DutyCycleDistortion	
EdgeAtLevel	
EMCIvIPulse	
EMCt2Val	
ExcelParam	
ExtinctionRatio	
EyeAmplitude	
EyeAvgPower	
EyeBER	
EyeCrossing	
EyeHeight	
EyeOneLevel	
EyeQFactor	
EyeZeroLevel	
FallAtLevel	
FastMultiWPort	
FrequencyAtLevel	
GapWidth	
HalfPeriod	
HoldTime	
HParamScript	
LevelAtX	
LocalBase	
LocalBaselineSeparation	
LocalMaximum	
LocalMinimum	
LocalNumber	
LocalPeakToPeak	
LocalTimeAtMaximum	
LocalTimeAtMinimum	
LocalTimeBetweenEvents	
LocalTimeBetweenPeaks	
LocalTimeBetweenTroughs	
LocalTimeOverThreshold	
LocalTimePeakToTrough	
LocalTimeTroughToPeak	

LocalTimeUnderThreshold	2-85
MathcadParam	2-86
MATLABParameter	2-88
Maximum	2-88

AVERAGE

app.Math.Fx.OperatorYSetup (Operator = "Average")

Waveform Averaging.

AverageType	Enum
ClearSweeps	Action
InvalidInputPolicy	Bool
Sweeps	Integer

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Turn trace F1 on and setup to average the data from C1
' Average mode is set to Continuous
app.Math.F1.View = True
app.Math.F1.Operator1 = "Average"
app.Math.F1.MathMode = "OneOpe
```

AverageType Enum

Description

Sets / Queries the averaging mode. Continuous and Summation modes are supported.

Values

Continuous	
Summed	

ClearSweeps Action

Description

Clears all averaged sweeps.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Clear sweeps for average in trace F1.
app.Math.F1.Operator1Setup.ClearSweeps
```

InvalidInputPolicy Bool

Sweeps Integer

Range From 1 to 1000000 step 1

Description

Sets / Queries the number of sweeps to be averaged when trace Fx is set to averaging - continuous or summed.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set number of sweeps to be averaged in trace F1 as 20.
app.Math.F1.OperatorlSetup.Sweeps = 20
```

BOXCAR

app.Math.Fx.OperatorYSetup (Operator = "Boxcar")

Rectangular BoxCar filter (local running average) of specified length.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set the filter length for the boxcar function in trace F1
app.Math.F1.View = True
app.Math.F1.MathMode = "OneOperator"
app.Math.F1.Operator1 = "Boxcar"
app.Math.F1.Operator1Setup.
```

Length Integer

Range From 2 to 5000 step 1

Description

Sets / Queries the length, in samples, of the boxcar FIR filter (i.e. the running average of a local set of "length" points)

COPY

app.Math.Fx.OperatorYSetup (Operator = "Copy")

BatchSize	Integer
ResetCount	Action
WfCount	Double
WfCountText	String

BatchSize Integer

Range From 128 to 10000000 step 128

ResetCount

WfCount
Range From 0 to 1e+009 step 1

WfCountText

String

Range Any number of characters

CORRELATION

app.Math.Fx.OperatorYSetup (Operator = "Correlation")

Correlate a portion of one waveform with another.

CorrLength	Double
CorrStart	Double

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

- ' Configure correlation in F3 using a length of 3.5 divisions,
- ' starting at the first division.

app.Math.F3.View = True

app.Math.F3.Operator1 = "Correlation"

app.Math.F3.Operator1S

CorrLength Double

Range From 0.001 to 10 step 0.001

Description

Sets / Queries the length in graticule divisions of the section of the first input trace that is used in the calculation of correlation.

CorrStart Double

Range From 0 to 9.999 step 0.001

Description

Sets/Queries the position in graticule divisions of the start of the section of trace 1 that is used in the correlation function in trace Fx.

DEMODULATE

app.Math.Fx.OperatorYSetup (Operator = "Demodulate")

Bandwidth	Double
CarrierFrequency	Double
DecimateBy	Integer
MaxCoefficients	Integer
SummaryText	String
Туре	Enum

Bandwidt	h	Double
Range	From 100000 to 1e+011 step 1000	
CarrierFre	equency	Double
Range	From 1e+006 to 1e+011 step 1	
Decimatel	Ву	Integer
Range	From 1 to 1000 step 1	
MaxCoeffi	icients	Integer
Range	From 9 to 8193 step 1	
Summary	Text	String
Range	Any number of characters	
Туре		Enum

Values

Amplitude	
Frequency	
Imaginary	
Phase	
Real	
Time	
WideBandAM	

DERIVATIVE

app.Math.Fx.OperatorYSetup (Operator = "Derivative")

Computes the derivative of the waveform (next_sample_value - this_sample_value) / horizontal_sample_interval.

EnableAutoScale	Bool
FindScale	Action
VerOffset	Double
VerScale	DoubleLockstep

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Start a find scale operation for derivative function trace F1
app.Math.F1.View = True
app.Math.F1.MathMode = "OneOperator"
app.Math.F1.Operator1 = "Derivative"
app.Math.F1.Operato
```

EnableAutoScale Bool

Description

Sets/Queries whether the autoscale function is enabled for the derivative function trace Fx. If enabled, an auto-scale operation is performed whenever the setup changes.

FindScale Action

Description

Initiates a Find Scale action, to set a suitable vertical scale for the derivative function trace Fx.

VerOffset Double

Range From -1e+006 to 1e+006 step 1e-009

Description

Sets/Queries the vertical offset of the derivative function trace Fx.

VerScale DoubleLockstep

Range From 1e-012 to 1e+013 step 10000, locked to 1 2 5, fine grain allowed=false, on=false

Description

Sets/Queries the vertical scale of the derivative function Fx.

DESKEW

app.Math.Fx.OperatorYSetup (Operator = "Deskew")

Deskew waveform by shifting it in time.

WaveDeskew Double

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Set the displacement of the trace F3 to 3.7e-9
app.Math.F3.View = True
app.Math.F3.MathMode = "OneOperator"
app.Math.F3.Operator1 = "Deskew"
app.Math.F3.Operator1Setup.WaveDeskew
```

WaveDeskew Double

Range From -2.5e-008 to 2.5e-008 step 1e-012

Description

Sets/Queries the displacement in time of the trace Fx. A positive value delays the signal: a negative one makes it appear earlier.

ENHANCEDRESOLUTION

app.Math.Fx.OperatorYSetup (Operator = "EnhancedResolution")

Bits Enum

Description

Number of bits of enhanced resolution. ERES is a FIR filter with a gaussian frequency response.

Values

0.5	Enhance by 0.5 bits
1	Enhance by 1 bits
1.5	Enhance by 1.5 bits
2	Enhance by 2 bits
2.5	Enhance by 2.5 bits
3	Enhance by 3 bits

ENVELOPE

app.Math.Fx.OperatorYSetup (Operator = "Envelope")

Envelope of minimum and maximum values for an ensemble of sweeps, or 'Extrema'

ClearSweeps	Action
LimitNumSweeps	Bool
Sweeps	Integer

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Configure F3 to be an envelope of C1
app.Math.F3.View = True
app.Math.F3.Source1 = "C1"
app.Math.F3.MathMode = "OneOperator"
app.Math.F3.Operator1 = "Envelope"
app.Math.F3.Operat
```

ClearSweeps Action

Description

Initiates a Clear Sweeps operation for envelope function trace Fx.

LimitNumSweeps Bool

Sweeps Integer

Range From 1 to 1000000 step 1

Description

Sets/Queries the maximum number of sweeps to be used by the envelope function trace Fx.

EXCELMATH

app.Math.Fx.OperatorYSetup (Operator = "ExcelMath")

Perform Math in Excel. Transfers 1 or 2 waveforms into Excel and reads the resulting waveform.

AddChart	Action
AddChart	Action

AddLabels	Action
Advanced	Bool
ClearSheet	Action
CreateDemoSheet	Action
FindScale	Action
NewSheet	Bool
OutputCell	String
OutputEnable	Bool
OutputHeaderCell	String
Scaling	Enum
Source1Cell	String
Source1Enable	Bool
Source1HeaderCell	String
Source2Cell	String
Source2Enable	Bool
Source2HeaderCell	String
SpreadsheetFilename	FileName
Status	String
WithHeader	Bool

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Configure F3 to process C1 in Excel using a demo-sheet app.Math.F3.View = True app.Math.F3.Source1 = "C1" app.Math.F3.MathMode = "OneOperator" app.Math.F3.Operator1 = "ExcelMath"□
```

AddChart Action

Description

Adds a chart to the current Excel spreadsheet.

AddLabels Action

Description

Adds labels to the cells of the array headers in the Excel spreadsheet.

Advanced Bool

Description

Enables/Disables/Queries the advanced Excel settings. By default, the cell ranges used to store the input waveform, and to retrieve the calculated waveform, are preset. Advanced mode allows these to be changed.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set function trace F3 to be an Excel function.
app.Math.F3.Operator1 = "ExcelMath"
' Enable the use of the advanced settings.
app.Math.F3.Operator1Setup.Advanced = True
```

ClearSheet Action

Description

Clears the contents of the current Excel spreadsheet.

CreateDemoSheet Action

Description

Creates a 'demo sheet', an excel spreadsheet pre-labelled, and with the output column equation preset to invert the input data.

FindScale Action

Description

Set a suitable scale for the output data from Excel on the instrument graticule when scaling has been set to manual.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Set function trace F3 to be an Excel function.
app.Math.F3.Operator1 = "ExcelMath"

' Set the scaling from the Excel spreadsheet to automatic.
app.Math.F3.Operator1Setup.Scaling = "Manual"

' Find a suitable scale for the output data
' on the instrument graticule.
app.Math.F3.Operator1Setup.FindScale
```

NewSheet Bool

Description

Enables/Disables/Queries the creation of a new Excel spreadsheet. If a new sheet is not to be created, an existing file name must be specified in the SpreadsheetFilename control.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

- ' Set function trace F3 to be an Excel function.
 app.Math.F3.Operator1 = "ExcelMath"
- ' Enable the creation of a new Excel spreadsheet. app.Math.F3.Operator1Setup.NewSheet = True

OutputCell String

Range Any number of characters

Description

Sets/Queries the cell label for output in the Excel function Fx. This cell marks the start (top) of the array of data to be taken from Excel into the instrument.

OutputEnable Bool

Description

Enables/Disables/Queries the transfer of output data from Excel to the instrument. If a one-way computation is required, where results of the Excel processing are not required, this should be set to False to increase performance.

OutputHeaderCell String

Range Any number of characters

Description

Sets/Queries the header cell label for output in the Excel function Fx. This is the starting cell for the header which carries setup information about the output waveform, from Excel to the instrument. Only used if the WithHeader control is set to True.

Scaling Enum

Description

Sets/Queries the method of scaling the output trace from the Excel spreadsheet.

Values

Automatic	Automatically scale the output waveform to full-scale
FromSheet	Retrieve scaling information from the output header in the spreadsheet
Manual	Manually auto-scale when FindScale is pressed

Source1Cell String

Range Any number of characters

Description

Sets/Queries the cell label for source 1 in the Excel function Fx. This cell marks the start (top) of the array into which data from the first source waveform is transferred.

Source1Enable Bool

Description

Enables/Disables/Queries the transfer of source 1 data from the instrument to Excel.

Source1HeaderCell String

Range Any number of characters

Description

Sets/Queries the header cell label for source 1 in the Excel function Fx. This is the starting cell for the header which carries setup information about waveform 1, from the instrument to Excel. This information includes waveform length, vertical and horizontal units, vertical and horizontal framing information, and horizontal scaling and offset information. Only used when the WithHeader control is set to True.

Source2Cell String

Range Any number of characters

Description

Sets/Queries the cell label for source 2 in the Excel function Fx. This cell marks the start (top) of the array into which data from the second source waveform is transferred.

Source2Enable Bool

Description

Enables/Disables/Queries the transfer of source 2 data from the instrument to Excel.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set function trace F1 to be an Excel function.
app.Math.F1.Operator1 = "ExcelMath"
' Enable the transfer of source 2 data from the instrument to Excel.
app.Math.F1.Operator1Setup.Source2Enable = True
```

Source2HeaderCell String

Range Any number of characters

Description

Sets/Queries the header cell label for source 2 in the Excel function Fx. This is the starting cell for the header which carries setup information about waveform 2, from the instrument to Excel. This information includes waveform length, vertical and horizontal units, vertical and horizontal framing information, and horizontal scaling and offset information. Only used when the WithHeader control is set to True.

SpreadsheetFilename

FileName

Range Any number of characters

Description

Sets/Queries the file name of the current Excel spreadsheet.

Example

- ' Visual Basic Script
 Set app = CreateObject("LeCroy.XStreamDSO")
- ' Set function trace F3 to be an Excel function. app.Math.F3.Operator1 = "ExcelMath"
- ' Disable the creation of a new Excel spreadsheet. app.Math.F3.Operator1Setup.NewSheet = False
- 'Select the filename of the existing Excel spreadsheet to be used. app.Math.F3.Operator1Setup.SpreadsheetFilename = "C:\Sheet17.xls"

Status String

Range Any number of characters

Description

Inspects the status of the Excel and instrument combination. Examples are "OK", or "Excel not installed".

WithHeader Bool

Description

Enables/Disables/Queries the presence of headers with the waveform data.

FASTWAVEPORT

app.Math.Fx.OperatorYSetup (Operator = "FastWavePort")

MaxSize	Integer
PortName	String
Timeout	Double

MaxSize Integer

Range From 0 to 100000000 step 1

PortName String

Range Any number of characters

Timeout Double

Range From 0 to 100 step 1

FFT

app.Math.Fx.OperatorYSetup (Operator = "FFT")

Fast Fourier Transform of waveform data.

Algorithm	Enum
FillType	Enum
SuppressDC	Bool
Туре	Enum
Window	Enum

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Configure F3 to perform an FFT of C1
app.Math.F3.View = True
app.Math.F3.Source1 = "C1"
app.Math.F3.MathMode = "OneOperator"
app.Math.F3.Operator1 = "FFT"
app.Math.F3.Operator1Se
```

Algorithm Enum

Description

Sets/Queries the algorithm for the FFT in function trace Fx.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set function trace F4 to FFT.
app.Math.F4.Operator1 = "FFT"
' Set the FFT algorithm to power of two.
app.Math.F4.Operator1Setup.Algorithm = "Power2"
```

Values

LeastPrime	
Power2	

FillType Enum

Description

Sets/Queries the type of trace fill to use in the FFT function trace Fx.

Values

Truncate	
ZeroFill	

SuppressDC Bool

Description

Enables/Disables suppression of the value at zero frequency in the FFT spectrum.

Type Enum

Description

Sets/Queries the type of FFT spectrum for function trace Fx.

Values

Imaginary	Imaginary part of the complex spectrum
Magnitude	Magnitude with linear vertical scale
MagSquared	
Phase	Phase
PowerDensity	Power Density
PowerSpectrum	Power Spectrum
Real	Real part of the complex spectrum

Window Enum

Description

Sets/Queries the type of window for the FFT function trace Fx.

Values

BlackmanHarris	
FlatTop	
Hamming	
Rectangular	
VonHann	

FILTER

app.Math.Fx.OperatorYSetup (Operator = "Filter")

Processes waveform using specified digital filter.

AutoLength	Bool
FilterKind	Enum
FIRMissingPointsLocation	Enum
FirOrlir	Enum
FitAlways	Bool
LowFreqPass	Double
NumberOfTaps	Integer
PassBandRipple	Double
ReframeOutput	Bool
SampleRateText	String
StopBandAttenuation	Double
TransitionWidth	Double

Example

' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Configure F1 to filter C1 app.Math.F1.View = True

app.Math.F1.Source1 = "C1"
app.Math.F1.MathMode = "OneOperator"
app.Math.F1.Operator1 = "Filter"
app.Math.F1.Operator1Setup.FirO

AutoLength Bool

Description

Enables/Disables/Queries status of the auto-length feature for the filter Fx.

FilterKind Enum

Description

Sets/Queries kind of filter to use in function Fx.

Values

BandPass	
BandStop	
Custom	
Gaussian	
HighPass	
LowPass	
RaisedCosine	
RaisedRootCosine	

FIRMissingPointsLocation

Enum

Values

Left	
LeftRight	
Right	

FirOrlir Enum

Description

Sets/Queries whether the filter Fx is an FIR filter or an IIR filter.

Values

FIR	Finite Impulse Response Filter
IIR	Infinite Impulse Response Filter

FitAlways Bool

LowFreqPass Double

Range From 1000 to 1e+011 step 1

Description

Sets/Queries the lower cut-off frequency for the band-pass filter Fx.

NumberOfTaps Integer

Range From 3 to 2001 step 1

Description

Sets/Queries the number of taps in the filter Fx. Valid only when the AutoLength control is set to False.

PassBandRipple

Double

Description

Range

Sets/Queries the pass-band ripple.

From 0.5 to 20 step 0.1

ReframeOutput Bool

SampleRateText String

Range Any number of characters

StopBandAttenuation Double

Range From 10 to 100 step 0.001

Description

Sets/Queries the stop-band attenuation of the filter Fx.

TransitionWidth Double

Range From 0 to 1e+011 step 1

Description

Sets/Queries the width of the transition in the frequency spectrum of filter Fx.

FLOOR

app.Math.Fx.OperatorYSetup (Operator = "Floor")

Most negative or minimum values for an ensemble of sweeps, or "Floor"

ClearSweeps	Action
LimitNumSweeps	Bool
Sweeps	Integer

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Configure F1 to measure the Floor of the first 1000
' sweeps of C1
app.Math.F1.View = True
app.Math.F1.Source1 = "C1"
app.Math.F1.MathMode = "OneOperator"
app.Math.F1.Operator1
```

ClearSweeps Action

Description

Initiates a clear sweeps action for the Floor function trace Fx.

LimitNumSweeps

Bool

Sweeps

Integer

Range From 1 to 1000000 step 1

Description

Sets/Queries the maximum number of sweeps for the Floor function trace Fx.

HISTOGRAM

app.Math.Fx.OperatorYSetup (Operator = "Histogram")

Histogram of the values of a parameter, or if a waveform is used as the input, histogram the waveform sample amplitudes.

AutoFindScale	Bool
Bins	DoubleLockstep
Center	Double
ClearSweeps	Action
FindScale	Action
HorScale	DoubleLockstep
Values	Integer
VerScaleType	Enum

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

- ' Configure F1 to histogram the first 200000 sample
- ' values from source waveform C1 into 50 bins.
- ' Auto find-scale is enabled.

app.Math.F1.View = True
app.Math.F1.Source1 = "C1"

AutoFindScale Bool

Description

Enables/Disables automatic scale setting for the histogram function Fx.

Bins DoubleLockstep

Range From 20 to 2000 step 1, locked to 1 2 5, fine grain allowed=false, on=false

Description

Sets/Queries the number of bins in the histogram function Fx.

Center Double

Range From -1e+010 to 1e+010 step 1e-012

Description

Sets/Queries the horizontal value at the center of the graticule of the histogram function Fx.

ClearSweeps Action

Description

Clears the contents of all the bins of the histogram function Fx.

FindScale Action

Description

Creates a suitable horizontal position and scale to include all the non-empty bins of the histogram Fx.

HorScale DoubleLockstep

Range From 1e-012 to 1e+012 step 0.01, locked to 1 2 5, fine grain allowed=false, on=false

Description

Sets/Queries the horizontal scale in units per division for the histogram function Fx. Use the FindScale control to automatically determine the scale by looking at the non-zero populated bins.

Values Integer

Range From 20 to 2000000000 step 1

Description

Sets/Queries the maximum number of values from the source result to include in the histogram function Fx.

VerScaleType Enum

Description

Sets/Queries the way that the vertical scale is calculated as the histogram Fx grows.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set function F1 as histogram.
app.Math.F1.Operator1 = "Histogram"
' Set the vertical scale type to linear with constant maximum.
app.Math.F1.Operator1Setup.VerScaleType = "LinConstMax"
```

Values

LinConstMax	Linear scale with constant maximum value
Linear	Linear scale

HTIE2BER

app.Math.Fx.OperatorYSetup (Operator = "Htie2BER")

Format	Enum
Frequency	Double
MaxPopInFit	DoubleLockstep
PercentileUsed	DoubleLockstep
TransitionDensity	Double
UseValInput	Bool
UseWeights	Bool

Format Enum

Values

Bathtub	
EstTIE	
LogEstTIE	
LogTIE	
TjGaussian	
TotalJitter	

Frequency Double

Range From 100000 to 1e+011 step 1

MaxPopInFit DoubleLockstep

Range From 10 to 1e+009 step 20, locked to 1 2 5, fine grain allowed=false, on=false

PercentileUsed DoubleLockstep

Range From 0.001 to 20 step 0.001, locked to 1 2 5, fine grain allowed=false, on=false

TransitionDensity Double

Range From 0.1 to 1 step 0.01

UseValInput Bool

UseWeights Bool

INTEGRAL

app.Math.Fx.OperatorYSetup (Operator = "Integral")

Integral of the linearly rescaled (multiplier and adder) input.

Adder	Double
AutoFindScale	Bool
FindScale	Action
Multiplier	Double
VerOffset	Double
VerScale	DoubleLockstep

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Configure F1 to integrate C1
app.Math.F1.View = True
app.Math.F1.Source1 = "C1"
app.Math.F1.MathMode = "OneOperator"
```

app.Math.F1.Operator1 = "Integral"
app.Math.F1.Operator1Setup

Adder Double

Range From -1e-009 to 1e-009 step 1e-012

Description

Sets/Queries the additive A for the integral function Fx, where Fx = M. Input + A.

AutoFindScale Bool

Description

Set/Query the state of the 'AutoFindScale' cvar, which enables the automatic scaling of the Integral when the acquisition setup changes.

FindScale Action

Description

Initiates an action to find suitable vertical offset and scale for the integral function trace Fx.

Multiplier Double

Range From -1e+006 to 1e+006 step 1e-006

Description

Sets/Queries the multiplying constant M for the integral function Fx, where Fx = M . Input + A

VerOffset Double

Range From -1e+006 to 1e+006 step 1e-015

Description

Sets/Queries the vertical offset for the integral function trace Fx.

VerScale DoubleLockstep

Range From 1e-012 to 1e+007 step 0.01, locked to 1 2 5, fine grain allowed=false, on=false

Description

Sets/Queries the vertical scale for the integral function trace Fx.

INTERPOLATE

app.Math.Fx.OperatorYSetup (Operator = "Interpolate")

Interpolate, producing more points in the resulting waveform using linear, cubic, or weighted sin(x)/x algorithms.

DownFactor	Action
Expand	DoubleLockstep
HalfWidth	Integer
InterpolateType	Enum
KaiserBeta	Double
NoiseGain	Double
UpFactor	Action
USE_1_2_5	Bool

WindowType Enum **Example** ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO") ' Configure F1 to interpolate C1 app.Math.F1.View = True app.Math.F1.Source1 = "C1" app.Math.F1.MathMode = "OneOperator" app.Math.F1.Operator1 = "Interpolate" app.Math.F1.Operator1 **DownFactor** Action DoubleLockstep **Expand** From 2 to 50 step 0.1, locked to 1 2 5, fine grain allowed=false, on=false Range Description Sets/Queries the sampling expansion ratio for the interpolation function Fx. HalfWidth Integer From 4 to 128 step 1 Range InterpolateType Enum Description Sets/Queries the type of interpolation for the function trace Fx. **Values** Cubic Linear SinXX **KaiserBeta** Double From 2 to 11 step 0.1 Range **NoiseGain** Double From 0.01 to 4 step 0.01 Range **UpFactor** Action USE_1_2_5 Bool

WindowType Enum

Values

Blackman	
BlackmanHarris	
Hamming	
Kaiser	
Rectangular	
VonHann	

ISIPATT

app.Math.Fx.OperatorYSetup (Operator = "ISIPatt")

AutoClearSweeps	Bool
BitRate	Double
ClearSweeps	Action
DelayPct	Double
NumberOfBits	Integer
Resample	Bool
UpdateVoltageTrack	Bool
UseBitRate	Bool
Width	Double

AutoClearSweeps	Bool
BitRate	Double
Range From 99000 to 2e+010 step 1000	
ClearSweeps	Action
Description Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.	
DelayPct	Double
Range From 0 to 100 step 0.01	
NumberOfBits	Integer
Range From 3 to 12 step 1	
Resample	Bool
UpdateVoltageTrack	Bool
UseBitRate	Bool

Width Double

Range From 1e-011 to 0.1 step 1e-012

LOWPASSIIR

app.Math.Fx.OperatorYSetup (Operator = "LowPassIIR")

Cutoff	Double
FilterType	Enum
Log2BuffSize	Integer
Order	Integer
Ripple	Double
Warning	String

Cutoff		Double
Range	From 10000 to 5e+011 step 1000	
FilterType		Enum
Values		
	Butterworth	
	Chebyshev1	
Log2BuffS	iize	Integer
Range	From 10 to 17 step 1	
Order		Integer
Range	From 1 to 12 step 1	
Ripple		Double
Range	From 0.01 to 4 step 0.01	

MATHCADMATH

String

app.Math.Fx.OperatorYSetup (Operator = "MathcadMath")

Produces a waveform using a user specified Mathcad function.

Any number of characters

Warning

Range

Advanced	Bool
FindScale	Action
NewSheet	Bool
OutputEnable	Bool

OutputHeaderVar	String
OutputVar	String
Reload	Action
Scaling	Enum
Source1Enable	Bool
Source1HeaderVar	String
Source1Var	String
Source2Enable	Bool
Source2HeaderVar	String
Source2Var	String
Status	String
WithHeader	Bool
WorksheetFilename	FileName

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Configure F1 to process C1 using Mathcad app.Math.F1.View = True app.Math.F1.Source1 = "C1" app.Math.F1.MathMode = "OneOperator" app.Math.F1.Operator1 = "MathcadMath"
```

Advanced Bool

Description

Enables/Disables/Queries the use of the advanced features. When in advanced mode the names used for source and output vectors, in addition to names used for source and output headers, may be modified from their default values.

FindScale Action

Description

Set a suitable vertical scale of the Mathcad output trace on the instrument graticule. Valid only when Manual scaling is specified.

NewSheet Bool

Description

Enables/Disables/Queries the creation of a new Mathcad worksheet.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set function F1 as Mathcad calculation.
app.Math.F1.Operator1 = "MathcadMath"
' Enable creation of a new Mathcad worksheet.
app.Math.F1.Operator1Setup.NewSheet = True
```

OutputEnable Bool

Description

Enables/Disables/Queries the transmission of output data from Mathcad to the instrument.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set function F1 as Mathcad calculation.
app.Math.F1.Operator1 = "MathcadMath"
' Enable transmission of output data.
app.Math.F1.Operator1Setup.OutputEnable = True
```

OutputHeaderVar String

Range Any number of characters

Description

Sets/Queries the name in Mathcad of the output header variable.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set function F1 as Mathcad calculation.
app.Math.F1.Operator1 = "MathcadMath"
' Enables use of headers.
app.Math.F1.Operator1Setup.WithHeader = True
' Sets the name of the output header variable
app.Math.F1.Operator1Setup.OutputHeaderVar = "header1"
```

OutputVar String

Range Any number of characters

Description

Sets/Queries the name in Mathcad of the output variable.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set function F1 as Mathcad calculation.
app.Math.F1.Operator1 = "MathcadMath"
' Sets the name of the output variable in Mathcad.
app.Math.F1.Operator1Setup.OutputVar = "output3"
```

Reload Action

Description

Reloads a specified Mathcad worksheet. If the worksheet does exist, the system creates an empty one with a name of the form "UntitledN", where N is an integer.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set function F1 as Mathcad calculation.
app.Math.F1.Operator1 = "MathcadMath"
' Specifies a Mathcad worksheet name.
app.Math.F1.Operator1Setup.WorksheetFilename = "XStream34.mcd"
' Reload a Mathcad worksheet.
app.Math.F1.Operator1Setup.Reload
```

Scaling Enum

Description

Sets/Queries the method of vertical scaling of the Mathcad output trace on the instrument graticule.

Values

Automatic	
Manual	

Source1Enable Bool

Description

Enables/Disables/Queries the transmission of source 1 data from the instrument to Mathcad.

Source1HeaderVar String

Range Any number of characters

Description

Sets/Queries the name in Mathcad of input 1 header variable.

Source1Var String

Range Any number of characters

Description

Sets/Queries the name in Mathcad of input variable 1.

Source2Enable Bool

Description

Enables/Disables/Queries the transmission of source 2 data from the instrument to Mathcad.

Source2HeaderVar String

Range Any number of characters

Description

Sets/Queries the name in Mathcad of input 2 header variable.

Source2Var String

Range Any number of characters

Description

Sets/Queries the name in Mathcad of input variable 2.

Status String

Range Any number of characters

Description

Inspects the status of the Mathcad calculation.

WithHeader Bool

Description

Enables/Disables/Queries inclusion of headers in the Mathcad calculation.

WorksheetFilename FileName

Range Any number of characters

Description

Sets/Queries a Mathcad worksheet file name.

MATLABWAVEFORM

app.Math.Fx.OperatorYSetup (Operator = "MATLABWaveform")

Process a waveform using an external MATLAB application.

MATLABCode	String
MATLABPlot	Bool
MATLABScalePerDiv	Double
MATLABZeroOffset	Double

MATLABCode String

Range Any number of characters

Description

String containing the MATLAB code to execute when new data is presented.

MATLABPlot Bool

Description

If true, the result of the MATLAB processing operation is plotted by MATLAB, in a floating window.

MATLABScalePerDiv Double

Range From 1e-009 to 1e+009 step 1e-009

Description

Vertical Scaling, used to scale the waveform returned from MATLAB to the DSO's graticule.

MATLABZeroOffset Double

Range From -1e+009 to 1e+009 step 1e-009

Description

Zero Offset (vertically), used to scale the waveform returned from MATLAB to the DSO's graticule.

PERSISTENCEHISTOGRAM

app.Math.Fx.OperatorYSetup (Operator = "PersistenceHistogram")

CenterCursor	Action
ClearSweeps	Action
CutDirection	Enum
VerCutCenter	Double
VerCutWidth	Double

CenterCursor Action

Description

Center the slice about the center of the axis, Vertical or Horizontal, depending upon the CutDirection Setting.

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

CutDirection Enum

Description

Specifies either a "vertical" cut direction or "horizontal" cut direction producing a histogram with the same horizontal coordinates as the chosen direction.

Values

Horizontal	
Vertical	

VerCutCenter Double

Range From -1.79769e+308 to 1.79769e+308 step 0

Description

Horizontal coordinate of center of cut or slice from the persistence map (in horizontal units)

VerCutWidth Double

Range From -1.79769e+308 to 1.79769e+308 step 0

Description

Horizontal coordinate of center of cut or slice from the persistence map (in horizontal units)

PERSISTENCETRACEMEAN

app.Math.Fx.OperatorYSetup (Operator = "PersistenceTraceMean")

ClearSweeps	Action
NumPoints	Integer

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

NumPoints Integer

Range From 100 to 100000 step 1

PERSISTENCETRACERANGE

app.Math.Fx.OperatorYSetup (Operator = "PersistenceTraceRange")

ClearSweeps	Action
NumPoints	Integer
PctPopulation	Double

ClearSweeps Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

NumPoints Integer

Range From 100 to 100000 step 1

PctPopulation Double

Range From 0.5 to 100 step 0.5

PERSISTENCETRACESIGMA

app.Math.Fx.OperatorYSetup (Operator = "PersistenceTraceSigma")

ClearSweeps	Action
NumPoints	Integer
Sigma	Double

ClearSweeps Action

	ratomation command and catory	Troid office mariaar 1 10000001 Troid office	
Descript Clea		ample to restart an average, or parameter statistics.	
NumPoint	· • · · · · · · · · · · · · · · · · · ·		Integer
	From 100 to 100000 step 1		mogor
Range	From 100 to 100000 step 1		
Sigma			Double
Range	From 0.5 to 10 step 0.1		
	·		
		D	EFRAME
		app.Math.Fx.OperatorYSetup (Operator	
		app.iviair.i x.operator roctup (operator -	- Kellallie)
	Fishlingur	Park	
	FitAlways FitOnInpDefChanged	Bool Bool	
	OneClickLarger	Bool	
	UseRegion	Enum	
	VerFrameStart	Double	
	VerFrameStop	Double	
			Book
FitAlways			Bool
FitOnInpD	DefChanged		Bool
OneClickl	_arger		Bool
UseRegio	n		Enum
Values			
	All		
-	Lower		
	Upper		
VerFrame	Start		Double
Range	From -1e+012 to 1e+012 step 1e-015		
VerFrame	Stop		Double
Range	From -1e+012 to 1e+012 step 1e-015		
		F app.Math.Fx.OperatorYSetup (Operator	RESCALE = "Rescale")
Linearly tran	nsform the vertical values of a waveform.	· · · · · · · · · · · · · · · · · · ·	

Adder

Double

CustomUnit	Bool
Multiplier	Double

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Configure F1
app.Math.F1.View = True
app.Math.F1.Source1 = "C1"
app.Math.F1.MathMode = "OneOperator"
app.Math.F1.Operator1 = "Rescale"
app.Math.F1.Operator1Setup.Adder = 2.0
app
```

Adder Double

Range From -1e+018 to 1e+018 step (9 digits)

Description

Sets/Queries the additive constant A in the rescale function Fx = M.Input + A

CustomUnit Bool

Description

Enables/Disables the application of a custom unit of measurement to the rescale function trace Fx.

Multiplier Double

Range From -1e+018 to 1e+018 step (9 digits)

Description

Sets/Queries the multiplicative constant M in the rescale function Fx = M.Input + A

ROOF

app.Math.Fx.OperatorYSetup (Operator = "Roof")

Most positive or maximum values for an ensemble of sweeps, or "Roof"

ClearSweeps	Action
LimitNumSweeps	Bool
Sweeps	Integer

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Configure F1 to measure the Roof of the first 1000
'sweeps of C1
app.Math.F1.View = True
app.Math.F1.Source1 = "C1"
app.Math.F1.MathMode = "OneOperator"
app.Math.F1.Operator1 =
```

ClearSweeps Action

Description

Initiates a clear sweeps action for the roof function trace Fx.

LimitNumSweeps

Bool

Sweeps

Integer

Range From 1 to 1000000 step 1

Description

Sets/Queries the maximum number of sweeps for the Roof function trace Fx.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Set function trace F2 to roof.
app.Math.F2.Operator1 = "Roof"
' Set the maximum number of sweeps to 150.
app.Math.F2.Operator1Setup.Sweeps = 150
```

SEGMENTSELECT

app.Math.Fx.OperatorYSetup (Operator = "SegmentSelect")

NumSelectedSegments	Integer
SelectedSegment	Integer

NumSelectedSegments

Integer

Range From 1 to 1 step 1

SelectedSegment

Integer

Range From 1 to 1 step 1

SEQBUILDER

app.Math.Fx.OperatorYSetup (Operator = "SeqBuilder")

ClearSweeps	Action
FifoMode	Bool
MaxWaveforms	Integer
StatusText	String
Sweeps	Integer

ClearSweeps

Action

Description

Clear any accumulated result data. Useful for example to restart an average, or parameter statistics.

Mode	Bool
«Waveforms	Integer
Range From 1 to 5000 step 1	
tusText	String
Range Any number of characters	
eeps	Integer
Range From 1 to 5000 step 1	
SE app.Math.Fx.OperatorYSetup (Opera	EQUENCEAVERAGE ator = "SequenceAverage"
Account to the second to the s	F
AverageType ClearSweeps	Enum Action
ConfirmFull	Action
Sweeps	Integer
erageType	Enum
Values	
Continuous	
Summed	
arSweeps	Action
Description Clear any accumulated result data. Useful for example to restart an average, or paral	meter statistics.
nfirmFull	Action
Range From 1 to 1000000 step 1	Integer
	SINXOVERX
	O (Operator = "SinXOverX")

SPARSE

app.Math.Fx.OperatorYSetup (Operator = "Sparse")

Waveform sparser, will reduce the number of points in the output waveform by skipping points in the input, and starting at a given offset.

SparsingFactor	Integer
SparsingPhase	Integer

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Configure F1 to sparse C1 by a factor of 100
app.Math.F1.View = True
app.Math.F1.Source1 = "C1"
app.Math.F1.MathMode = "OneOperator"
app.Math.F1.Operator1 = "Sparse"
app.Math.F1.
```

SparsingFactor Integer

Range From 1 to 1000000 step 1

Description

Sets/Queries the factor by which the number of samples is reduced in the sparsing function Fx.

SparsingPhase Integer

Range From 0 to 0 step 1

Description

Sets/Queries the number of the first sample that will be accepted by the sparsing function Fx.

TREND

app.Math.Fx.OperatorYSetup (Operator = "Trend")

Trend of the values of a parameter, if connected to a parameter result source, or a trend of the sample values of a waveform, if connected to a waveform result source.

AutoFindScale	Bool
Center	Double
ClearSweeps	Action
FindScale	Action
Mode	Enum
Values	Integer
VerScale	DoubleLockstep

AutoFindScale Bool

Description

Enables/Disables the automatic setting of the vertical scale and vertical offset for the trend trace Fx.

Center Double

Range From -1.79769e+308 to 1.79769e+308 step 0

Description

Sets/Queries the vertical position of the centre of the trend trace Fx.

ClearSweeps Action

Description

Clears the contents of the trend trace Fx.

FindScale Action

Description

Sets the vertical scale and offset to optimum values to display the trend trace Fx.

Mode Enum

Description

Trend mode, defines which parameter measurements are used to build the trend.

Values

All	Trend all values
AllperTrace	Trend an average of all values per acquisition
Average	Trend all values per trace, clear before new acquisition.

Values Integer

Range From 2 to 1000000 step 1

Description

Sets/Queries the number of visible values in the trend trace Fx.

VerScale DoubleLockstep

Range From 1e-015 to 1e+012 step 0.01, locked to 1 2 5, fine grain allowed=false, on=false

Description

Sets/Queries the vertical scale of the trend trace Fx.

WAVESCRIPT

app.Math.Fx.OperatorYSetup (Operator = "WaveScript")

Code	String
Language	Enum
Status	String
Timeout	Double

Code String

Range Any number of characters

Values JScript VBScript Status Range Any number of characters Fnum String

Range From 1 to 1200 step 0.001

MATHCADPARAMARITH

app.Measure.Px.Operator (ArithEngine = "MathcadParamArith")

Advanced	Bool
NewSheet	Bool
OutputEnable	Bool
OutputHeaderVar	String
OutputVar	String
Reload	Action
Source1Enable	Bool
Source1HeaderVar	String
Source1Var	String
Source2Enable	Bool
Source2HeaderVar	String
Source2Var	String
Status	String
WithHeader	Bool
WorksheetFilename	FileName

Advanced Bool

Description

Enables/Disables/Queries use of advanced features fro Mathcad parameter Px.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Set parameter P3 as Mathcad calculation. app.Measure.P3.ParamEngine = "MathcadParam" ' Enables use of advanced features. app.Measure.P3.Operator.Advanced = True NewSheet Bool

Description

Enables/Disables/Queries use of new Mathcad worksheet for parameter Px.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
' Enable new Mathcad worksheet.
app.Measure.P3.Operator.NewSheet = True
```

OutputEnable Bool

Description

Enables/Disables/Queries transmission of output data from Mathcad to instrument.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

' Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
' Enables transmission of Mathcad output to the instrument.
app.Measure.P3.Operator.OutputEnable = True
```

OutputHeaderVar String

Range Any number of characters

Description

Sets/Queries the name of the output variable header in Mathcad parameter Px.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
' Sets the name of the Mathcad output header variable
app.Measure.P3.Operator.OutputHeaderVar = "outputheader"
```

OutputVar String

Range Any number of characters

Description

Sets/Queries the name of the output variable in Mathcad parameter Px.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
' Sets the name of the Mathcad output variable
app.Measure.P3.Operator.OutputVar = "output7"
```

Reload Action

Description

Reloads the specified Mathcad file.

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
'Specfify a Mathcad worksheet filename.
app.Measure.P3.Operator.WorksheetFilename = "C:\XStreamMathcad\Param233.mcd"
'Reload the specified Mathcad file.
app.Measure.P3.Operator.Reload
```

Source1Enable Bool

Description

Enables/Disables/Queries transmission of source data 1 from instrument to Mathcad.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
' Enables transmission of source 1 data to instrument.
app.Measure.P3.Operator.Source1Enable = True
```

Source1HeaderVar String

Range Any number of characters

Description

Sets/Queries the name of the input variable 1 header in Mathcad parameter Px.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
' Sets the name of the Mathcad source 1 header variable
app.Measure.P3.Operator.Source1HeaderVar = "input1header"
```

Source1Var String

Range Any number of characters

Description

Sets/Queries the name of the input variable 1 in Mathcad parameter Px.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
' Sets the name of the source 1 variable
app.Measure.P3.Operator.Source1Var = "input1"
```

Source2Enable Bool

Description

Enables/Disables/Queries transmission of source data 2 from instrument to Mathcad.

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
'Enables transmission of source 2 data to instrument.
app.Measure.P3.Operator.Source2Enable = True
```

Source2HeaderVar String

Range Any number of characters

Description

Sets/Queries the name of the input variable 2 header in Mathcad parameter Px.

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
' Sets the name of the Mathcad source 2 header variable
app.Measure.P3.Operator.Source2HeaderVar = "input2header"
```

Source2Var String

Range Any number of characters

Description

Sets/Queries the name of the input variable 2 in Mathcad parameter Px.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"
' Sets the name of the source 2 variable
app.Measure.P3.Operator.Source2Var = "input2"
```

Status String

Range Any number of characters

Description

Inspects the status of the Mathcad parameter calculation Px.

Example

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"

'Inspect status of Mathcad parameter calculation.
MathcadStatus = app.Measure.P3.Operator.Status
```

WithHeader Bool

Description

Enables/Disables/Queries presence of headers with variables with Mathcad parameter Px.

```
'Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")

'Set parameter P3 as Mathcad calculation.
app.Measure.P3.ParamEngine = "MathcadParam"

'Enables inclusion of headers with data.
app.Measure.P3.Operator.WithHeader = True
```

WorksheetFilename FileName

Range Any number of characters

Description

Sets/Queries the name of the current Mathcad file for parameter Px.

Example

- ' Visual Basic Script
 Set app = CreateObject("LeCroy.XStreamDSO")
- ' Set parameter P3 as Mathcad calculation.
 app.Measure.P3.ParamEngine = "MathcadParam"
 ' Specfify a Mathcad worksheet filename.
 app.Measure.P3.Operator.WorksheetFilename =
 "C:\XStreamMathcad\Param233.mcd"

PARAMCONST

app.Measure.Px.Operator (ArithEngine = "ParamConst")

HorRes	Double
HorStartValue	Double
HorStopValue	Double
HorUnits	String
StatusValue	Integer
Value	Double
VerRes	DoubleLockstep
VerUnits	String

HorRes		Double
Range	From 1e-020 to 0.001 step 1e-020	
HorStartV	/alue	Double
Range	From -1e+012 to 1e+012 step 1e-015	
HorStopValue		Double
Range	From -1e+012 to 1e+012 step 1e-015	
HorUnits		String
Range	Any number of characters	
StatusVal	ue	Integer
Range	From 0 to 2147483647 step 1	

Value			Double
Range	From -1e+012 to 1e+012 step	1e-015	
VerRes		Do	oubleLockstep
Range	From 1e-015 to 1 step 1e-008,	locked to 1 2 5, fine grain allowed=false, on=false	
VerUnits			String
Range	Any number of characters		
		PA	RAMINVERT
		app.Measure.Px.Operator (ArithEngine	
	CycleForTimeUnits	Bool	
	6,500 6. 7		
CycleFor [*]	TimeUnits		Bool
		PAR	AMMINMAX
		app.Measure.Px.Operator (ArithEngine =	"ParamMinMax")
	MinMax	Enum	
MinMax			Enum
Values			
	Max		
	Min		
			MPASSTHRU
		app.Measure.Px.Operator (ArithEngine = "F	'aramPassThru")
	ShowButton	Bool	
ShowBut	ton		Bool
		PARA	MRESCALE
		app.Measure.Px.Operator (ArithEngine =	"ParamRescale")
	Adder	Double	

CustomUnit	Bool
Multiplier	Double

Adder Double

Range From -1.79769e+308 to 1.79769e+308 step 0

CustomUnit Bool

Multiplier Double

Range From -1.79769e+308 to 1.79769e+308 step 0

PARAMSCRIPT

app.Measure.Px.Operator (ArithEngine = "ParamScript")

Code	String
Language	Enum
Status	String
Timeout	Double

Code	String
------	--------

Range Any number of characters

Language Enum

Values

JScript	
VBScript	

Status String

Range Any number of characters

Timeout Double

Range From 1 to 12000 step 0.001

PLIMITER

app.Measure.Px.Operator (ArithEngine = "Plimiter")

MaxNbParam	Integer
StartParamldx	Integer

Range	From 1 to 1000000000 step 1		
StartParar	nldx		Integer
Range	From 0 to 1000000000 step 1		J
	·		
			100BTFALL
		app.Measure.Px.Operator (ParamEngi	
		· · · · · · · · · · · · · · · · · · ·	
	SelectedLevels	Enum	
SelectedL	ovolo		Enum
Selecteur	eveis		Enam
Values			
	Lower		
	Upper		
			4000000
		Alexander De Orangia (Description)	100BTRISE
		app.Measure.Px.Operator (ParamEngir	ne = "100B1rise")
	SelectedLevels	Enum	
SelectedL	evels		Enum
Values			٦
	Lower Upper		_
	Орреі		
			100BTTIE
		app.Measure.Px.Operator (ParamEngir	ne = "100BTTIE")
-			
	BaseFrequency	Double	
	FindBaseFrequency	Action	
	SelectedLevels	Enum	
BaseFrequ	uency		Double
Range	From 1 to 2e+012 step 10		
FindBasel	Frequency		Action

			Levels	SelectedL
			S	Values
7			Lower	
			Upper	
100BTTJ				
gine = "100BTTj")	rator (ParamEngir	app.Measure.Px.O		
	Double	uency	BaseFrequency	
	Action		FindBaseFrequency	
	Enum	evels	SelectedLevels	
Double			quency	BaseFreq
		+012 step 10	From 1 to 2e+012 ste	Range
Action			eFrequency	FindBase
Enum			Levels	SelectedL
			S	Values
7			Lower	
			Upper	
_				_
10BTJ				
ngine = "10BTJ",	perator (ParamEng	app.Measure.Px.		
	Action	eps	ClearSweeps	
Action			eps	ClearSwe
				Descript
stics.	or parameter statistic	ted result data. Useful for example to restart an average	ar any accumulated resu	Clea
ANADI ITUDE				
AMPLITUDE				
ne – "Amnlitude".	ator (ParamEngine	app.Measure.Px.Op		

app.Measure.Px.Operator (ParamEngine = "AmplitudeAsymmetry")

	Hysteresis		Double
lysteresis			
Range	From 0 to 10 step 0.1		

ANALOG2PROTOCOL

app.Measure.Px.Operator (ParamEngine = "Analog2Protocol")

AddressOperator	Enum
AddressValue	BitPattern
AddressValue2	BitPattern
FilterType	Enum
FindLevel	Action
Hysteresis	Double
LevelType	Enum
PatternBitLength	Integer
PatternBitPos	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
PercentLevel	Double
Slope	Enum
ViewingMode	Enum

AddressOperator Enum

Values

Equal	
Greater	
GreaterOrEqual	
InRange	
NotEqual	
OutRange	
Smaller	
SmallerOrEqual	

AddressValue BitPattern

Range MaxBits=32 NumBits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X PadAlign=Left SizeAlign=BitFix Format=Ehex

AddressVa	lue2	BitPat	tern
Range	MaxBits=32 NumBits=8 NumBytes PadAlign=Left SizeAlign=BitFix Fo	s=1 AllowedBitValues=01 PaddingChar=1 rmat=Ehex	
FilterType		EI	num
Values			
	Any		
	ID ID		
	IDData		
FindLevel		Ac	tion
Hysteresis		Do	uble
-	From 0 to 10 step 0.1		
LevelType		Е	num
Values			
	Absolute		
	Percent		
	PercentGNDMax		
	PercentGNDMin		
	PercentPkPk		
PatternBitL	ength.	Inte	eger
Range	From 1 to 128 step 1		
PatternBitF	Pos	Inte	eger
Range	From 0 to 127 step 1		
PatternOpe	erator	Eı	num
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
PatternVal	Je	BitPat	tern
Range	MaxBits=128 NumBits=8 NumByte PadAlign=Left SizeAlign=BitVar Fo	es=1 AllowedBitValues=01X PaddingChar=X	

BitPattern PatternValue2 MaxBits=128 NumBits=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 Range PadAlign=Left SizeAlign=BitVar Format=Ehex Double **PercentLevel** From 0 to 100 step 1 Range **Slope Enum Values** Both Bothneg **Bothpos** Neg Pos ViewingMode Enum **Values** Binary Hex **AREA** app.Measure.Px.Operator (ParamEngine = "Area") Calculates the area of the input waveform relative to zero. Cyclic Bool Example ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO") ' Set parameter P1 to area. app.Measure.P1.View = True app.Measure.P1.MeasurementType = "measure" app.Measure.P1.ParamEngine = "Area" app.Measure.P1.Source1 = "C1" ' Enable cycli Cyclic Bool Description

Enables/Disables cyclic calculation of area parameter Px, that is calculated using a whole number of cycles of the signal.

Note: the HelpMarkers aid in observing over which region of the waveform the measurement is made.

AUTOCORRELATIONSIGNALTONOISE

app.Measure.Px.Operator (ParamEngine = "AutoCorrelationSignalToNoise")

PatternLength	Double
i atternizengti	Double

PatternLength Double

Range From 1e-009 to 0.001 step 1e-010

BASE

app.Measure.Px.Operator (ParamEngine = "Base")

BURSTWIDTH

app.Measure.Px.Operator (ParamEngine = "BurstWidth")

AbsLevel1	Double
AbsLevel2	Double
BitRate	Double
LevelType	Enum
MaxRunLength	Integer

AbsLevel ²	1	Double
Range	From -100 to 100 step 0.0001	
AbsLevel	2	Double
Range	From -100 to 100 step 0.0001	
BitRate		Double
Range	From 0 to 1e+011 step 1000	
LevelType	e	Enum
Values		
	Absolute	
	Percent	
L	-	

Range From 2 to 20 step 1

MaxRunLength

CANLOAD

Integer

app.Measure.Px.Operator (ParamEngine = "CANLoad")

FrameType	Enum
FromID	String
IDBits	Enum
IDCondition	Enum
MessageCount	Bool
ToID	String

FrameTy _l	pe	Enun
Values	3	
	ALL	
	Data	
	Error	
	Remote	
romID		String
Range	Any number of characters	·
DBits		Enun
סווט		Enan
Values	3	
	ALL	
	EXT29bit	
	STD11bit	
DCondit	ion	Enun
Values	3	
	DontCare	
	EQ	
	GE	
	GT	
	INRANGE	
	LE	
	LT	
/lessage		Вос
Message FoID		Boo

app.Measure.Px.Operator (ParamEngine = "CANMsgBR")

CANMSGBR

FrameType	Enum
FromID	String
IDBits	Enum
IDCondition	Enum
ToID	String

FrameTy _l)e		Enum
Values			
	ALL		
	Data		
	Error		
	Remote		
FromID			String
Range	Any number of characte		
IDBits			Enum
Values			
	ALL		
	EXT29bit		
	STD11bit		
IDConditi	on		Enum
Values			
	DontCare		
	EQ		
	GE		
	GT		
	INRANGE		
	LE		
	LT		
ToID			String
Range	Any number of characte		
		CANI	MSGNUN
		app.Measure.Px.Operator (ParamEngine = "CA	I <i>IVIVISGI</i> VUM
		, , ,	
	FrameType	Enum	
	FromID	String	

Enum

IDBits

IDCondition	Enum
ToID	String

FrameTy	pe		Enum
Values	3		
	ALL		
	Data		
	Error		
	Remote		
FromID			String
	A	hovestore	og
Range	Any number of o	characters	
IDBits			Enum
Values	S		
	ALL		
	EXT29bit		
	STD11bit		
IDConditi			Enum
ibconditi	1011		Liidiii
Values	.		
	DontCare		
	EQ		
	GE		
	GT		
	INRANGE		
	LE		
	LT		
TolD			String
Range	Any number of o	characters	
	,		
			CANTOANALOC
			CANTOANALO
		app.Measure.Px.Operator (Pai	ramEngine = "CANtoAnalog
	DataConditio	n	Enum
	DataValue0		String
	DataValue1		String
	DataValue2		String
	DataValue3		String

String

DataValue4

DataValue5	String
DataValue6	String
DataValue7	String
DLC	Integer
FindLevel	Action
FrameType	Enum
Hysteresis	Double
ID	String
IDCondition	Enum
LevelType	Enum
PercentLevel	Double
Slope	Enum

DataCond	lition		Enum
Values			
	EQ		
	X		
DataValu	e0		String
Range	Any number of chara	cters	
DataValu	e1		String
Range	Any number of chara	octers	
DataValu	e2		String
Range	Any number of chara	octers	
DataValu	e3		String
Range	Any number of chara	cters	
DataValu	e4		String
Range	Any number of chara	octers	
DataValu	e5		String
Range	Any number of chara	octers	
DataValu	e6		String
Range	Any number of chara	octers	
DataValu	e7		String
Range	Any number of chara	octers	

DLC		Integer
Range	From 0 to 8 step 1	
		Agian
FindLevel		Action
FrameTyp	е	Enum
Values		
	Data	
_	Error	
-	Remote	
Hysteresi	S	Double
Range	From 0 to 10 step 0.1	
ID		String
		String
Range	Any number of characters	
IDCondition	on	Enum
Values		
	DontCare	
-	EQ	
-	GE	
	GT	
	INRANGE	
	LE	
	LT	
LevelType)	Enum
Values		
Values		
_	Absolute	
F	Percent	
_	PercentGNDMax	
	PercentGNDMin	
	PercentPkPk	
PercentLe	··	Double
	From 0 to 100 step 1	

Slope Enum

Values

Both	
Neg	
Pos	

CANTOCAN

app.Measure.Px.Operator (ParamEngine = "CANtoCAN")

DataCondition1	Enum
DataCondition2	Enum
DataValue01	String
DataValue02	String
DataValue11	String
DataValue12	String
DataValue21	String
DataValue22	String
DataValue31	String
DataValue32	String
DataValue41	String
DataValue42	String
DataValue51	String
DataValue52	String
DataValue61	String
DataValue62	String
DataValue71	String
DataValue72	String
DLC1	Integer
DLC2	Integer
FrameType1	Enum
FrameType2	Enum
ID1	String
ID2	String
IDCondition1	Enum
IDCondition2	Enum

DataCondition1 Enum

Values

EQ	
Χ	

DataCond	dition2		Enum
Values			
	EQ		
	X		
DataValu	e01		String
Range	Any number of chara	cters	
DataValu	e02		String
Range	Any number of chara	cters	
DataValu	e11		String
Range	Any number of chara	cters	
DataValu	e12		String
Range	Any number of chara	cters	
DataValu	e21		String
Range	Any number of chara	cters	
DataValu	e22		String
Range	Any number of chara	cters	
DataValu	e31		String
Range	Any number of chara	cters	
DataValu	e32		String
Range	Any number of chara	cters	
DataValu	e41		String
Range	Any number of chara	cters	
DataValu	e42		String
Range	Any number of chara	cters	
DataValu	e51		String
Range	Any number of chara	cters	
DataValu	e52		String
Range	Any number of chara	cters	

DataValue	e61	String
Range	Any number of characters	
DataValue	962	String
Range	Any number of characters	
DataValue	e71	String
Range	Any number of characters	
DataValue	e72	String
Range	Any number of characters	
DLC1		Integer
Range	From 0 to 8 step 1	
DLC2		Integer
Range	From 0 to 8 step 1	
FrameTyp	pe1	Enum
Values		
	Data	
	Error	
	Remote	
FrameTyp	pe2	Enum
Values		
	Data	
	Error	
	Remote	
ID1		String
Range	Any number of characters	
ID2		String
Range	Any number of characters	

DC anditio			Enum
DConditio	on1		Enum
Values			
	DontCare		
	EQ		
	GE		
	GT		
	INRANGE		
	LE		
	LT		
Conditio	on2		Enum
Values			
values	DontCare		
	EQ		
	GE		
	GT		
	INRANGE		
	LE		
	LT		
	Algorithm	app.Measure.Px.Operator (ParamEngine = "CAnger of the control of t	
	BitWidth	Integer	
	Coeff	Double	
	Format	Enum	
	ID	BitPattern	
	StartBit	Integer	
	Term	Double	
	Туре	Enum	
	Units	String	
lgorithm			Enum
Values			
	ByOption		
	ForceLecroy		
	ForceVector		

BitWidth		Integer
Range	From 1 to 32 step 1	
Coeff		Double
Range	From -1000 to 1000 step 1e-005	
Format		Enum
Values		
	Intel	
	Motorola	
ID		BitPattern
Range	MaxBits=29 NumBits=29 NumBytes=4 AllowedBitValues=01 Paddir PadAlign=Left SizeAlign=BitFix Format=Ehex	gChar=0
StartBit		Integer
Range	From 0 to 63 step 1	
Term		Double
Range	From -10000 to 10000 step 1e-005	
Туре		Enum
Values		
	SignedInt	
	UnsignedInt	
Units		String
Range	Any number of characters	

name 7 my mamber of characters

DELTAMESSAGES

app.Measure.Px.Operator (ParamEngine = "DeltaMessages")

AddressOperator	Enum
AddressValue	BitPattern
AddressValue2	BitPattern
FilterType	Enum
PatternBitLength	Integer
PatternBitPos	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
ViewingMode	Enum

AddressO	Operator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
Address\	/alue		BitPattern
Range		8 NumBytes=1 AllowedBitValues=01X PaddingChar=Xgn=BitFix Format=Ehex	
Address\	/alue2		BitPattern
Range		8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 gn=BitFix Format=Ehex	
FilterType	9		Enum
Values			
	Any		
	ID ID		
	IDData		
PatternBi	tLength		Integer
Range	From 1 to 128 step 1		
PatternBi	tPos		Integer
Range	From 0 to 127 step 1		
PatternO	perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		

PatternVa	alue		BitPattern
Range		s=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X ign=BitVar Format=Ehex	
PatternVa	alue2		BitPattern
Range		s=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 ign=BitVar Format=Ehex	
ViewingM	lode		Enum
Values			
	Binary		
•	Hex		
		DELTAPER app.Measure.Px.Operator (ParamEngine = "De	IODATLEVEL ItaPeriodAtLevel"
	FindLevel	Action	
	GroupSize	Integer	
	Hysteresis	Double	_
	LevelType	Enum	_
	PercentLevel	Double	-
	SignalType	Enum	-
	Slope	Enum	-
	StartCycle	Integer	_
	Summary	String	
FindLevel	I		Action
GroupSiz	e		Integer
Range	From 1 to 1024 step	1	
Hysteresi	S		Double
Range	From 0 to 10 step 0.1		
LevelType	e		Enum
Values			_
	Absolute		
	Percent		
	PercentGNDMax		
	PercentGNDMin		
	PercentPkPk		

PercentLe	vel	Double
Range	From 0 to 100 step 1	
SignalTyp	e	Enum
Values		
	Clock	
	Data	
Slope		Enum
Values		
	Both	
	Neg	
	Pos	
StartCycle	;	Integer
Range	From 0 to 0 step 1	
Summary		String
Range	Any number of characters	
		DEI TATIMEATI EVE

app.Measure.Px.Operator (ParamEngine = "DeltaTimeAtLevel")

FindLevel1	Action
FindLevel2	Action
Hysteresis1	Double
Hysteresis2	Double
LevelType1	Enum
LevelType2	Enum
PercentLevel1	Double
PercentLevel2	Double
Slope1	Enum
Slope2	Enum

FindLevel1 Action

Description

When in absolute level mode, finds the absolute level at 50% on the first trace

FindLevel2 Action

Description

When in absolute level mode, finds the absolute level at 50% on the second trace

Hysteresis1 Double From 0 to 10 step 0.1 Range Description Hysteresis in divisions around the level on first trace. The signal must enter the hysteresis zone (shown as a cursor) on one side and exit from the other side to qualify a transition. Hysteresis2 Double From 0 to 10 step 0.1 Range Description Hysteresis in divisions around the level on second trace. The signal must enter the hysteresis zone (shown as a cursor) on one side and exit from the other side to qualify a transition. LevelType1 **Enum** Description Type of level on first trace: absolute/percent and %Pkpk, %0-Min, %0-Max with EMC option **Values** Absolute Percent PercentGNDMax PercentGNDMin PercentPkPk LevelType2 Enum Description Type of level on second trace: absolute/percent and %Pkpk, %0-Min, %0-Max with EMC option. **Values** Absolute Percent PercentGNDMax PercentGNDMin PercentPkPk PercentLevel1 Double From 0 to 100 step 1 Range Description Level on first trace in percent. PercentLevel2 Double From 0 to 100 step 1 Range Description

Level on second trace in percent.

Slope1			Enum
Descrip	otion		
Sigr	n of detected transition on first trace: positive, ne	egative, both.	
Values	5		
	Both		
	Neg		
	Pos		
Slope2			Enum
	aki a u		
Descrip Sign	otion n of detected transition on second trace: positive	a negative both	
		, nogativo, both	
Values	5		
	Both		
	Neg		
	Pos		
		DEL TAMBELL	ATI EVE
		DELTAWIDTH	
	арр.Ме	asure.Px.Operator (ParamEngine = "DeltaV	/idthAtLevel"
	FindLevel	Action	
	Hysteresis	Double	
	LevelType	Enum	
	PercentLevel	Double	
	Support	Enum	
	Summary	String	
indLeve) 		Action
lysteres	is		Double
Range	From 0 to 10 step 0.1		
Nalige	1 10111 0 to 10 step 0.1		
.evelTyp	ee		Enum
Values	5		
	Absolute		
	Percent		
	PercentGNDMax		
	PercentGNDMin		
	PercentPkPk		

PercentLe	evel		Double
Range	From 0 to 100 step 1		
Slope			Enum
Values			
	Both		
	Neg		
	Pos		
Summary			String
		tore	Jg
Range	Any number of charac	lei S	
			DOV
		app.Measure.Px.Operator (Paran	nEngine = "DOV")
	SelectedLevels	Enum	
Calaataall			Enum
SelectedL	eveis		Enum
Values			
	Lower		
	Upper		
L			
		DU	JTYATLEVEL
		app.Measure.Px.Operator (ParamEngine	e = "DutyAtLevel")
	FindLevel	Action	
	Hysteresis	Double	
	LevelType	Enum	
	PercentLevel	Double	
	Slope	Enum	
	Summary	String	
FindLevel			Action
i ilideevel			
Hysteresis	8		Double
Range	From 0 to 10 step 0.1		
-			

LevelType	En	Enum	
Values			
	Absolute		
	Percent		
•	PercentGNDMax		
	PercentGNDMin		
	PercentPkPk		
PercentLe	evel	Dou	ıble
Range	From 0 to 100 step 1		
Slope		En	um
Values			
	Neg		
	Pos		
Summary		Str	ring
Range	Any number of characters		Cumg
	app.Measure.	Px.Operator (ParamEngine = "DutyCycleDisto	ortion")
	FindLevel	Action	
	Hysteresis	Double	
	LevelType	Enum	
	PercentLevel	Double	
	Slope	Enum	
FindLeve		Act	ion
Hysteresi	e	Dou	ıhle
Range	From 0 to 10 step 0.1	200	
LevelType	e	En	um
\/=l			
Values			
	Absolute		
	Percent PercentGNDMax		
	PercentGNDMin PercentGNDMin		
	PercentPkPk		
Į			

PercentLe	evel	Double
Range	From 0 to 100 step 1	
Slope		Enum
Values		
	Neg	
	Pos	
		EDGEATLEVEL
		app.Measure.Px.Operator (ParamEngine = "EdgeAtLevel"
	FindLevel	Action
	Hysteresis	Double
	LevelType	Enum
	PercentLevel	Double
	Slope	Enum
	Summary	String
FindLevel		Action
Hysteresi	s	Double
Range	From 0 to 10 step 0.1	
LevelType	;	Enum
Values		
	Absolute	
	Percent	
	PercentGNDMax	
	PercentGNDMin	
	PercentPkPk	
PercentLe	evel	Double
Range	From 0 to 100 step 1	
Slope		Enum
Values		
-	Both	
	Neg	
	Pos	

Summary String

Range Any number of characters

EMCLVLPULSE

app.Measure.Px.Operator (ParamEngine = "EMClvlPulse")

Delay	Double
Hysteresis	Double
LevelType	Enum
PercentLevel	Double
Slope	Enum

Delay		Double
Range	From 0 to 1 step 1e-012	
Hysteresi	S	Double
Range	From 0 to 10 step 0.1	
LevelType	e	Enum
Values		
	Absolute	
	Percent	
	PercentGNDMax	
	PercentGNDMin	
	PercentPkPk	
PercentLo	evel	Double
Range	From 0 to 100 step 1	
Slope		Enum
Values		
	Neg	
	Pos	

EMCT2VAL

app.Measure.Px.Operator (ParamEngine = "EMCt2Val")

LevelType	Enum
PercentHighLevel	Double
PercentLowLevel	Double

PercentMidLevel	Double
PulsePolarity	Enum

LevelType Enum

Values

Percent	
PercentGNDMax	
PercentGNDMin	
PercentPkPk	

PercentHighLevel Double

Range From 5 to 95 step 1

PercentLowLevel Double

Range From 5 to 95 step 1

PercentMidLevel Double

Range From 5 to 95 step 1

PulsePolarity Enum

Values

Neg	
Pos	

EXCELPARAM

app.Measure.Px.Operator (ParamEngine = "ExcelParam")

AddChart	Action
AddLabels	Action
Advanced	Bool
ClearSheet	Action
CreateDemoSheet	Action
NewSheet	Bool
OutputCell	String
OutputEnable	Bool
OutputHeaderCell	String
Source1Cell	String
Source1Enable	Bool
Source1HeaderCell	String
Source2Cell	String
Source2Enable	Bool
Source2HeaderCell	String

SpreadsheetFilename	FileName
Status	String
WithHeader	Bool

AddChart Action Description Adds a chart to the output worksheet **AddLabels** Action Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. **Advanced** Bool Description Sets/Queries whether advanced features of this component are accessible **ClearSheet** Action Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. CreateDemoSheet Action Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. **NewSheet** Bool Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. **OutputCell** String Range Any number of characters Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. **OutputEnable** Bool Description

Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath

function.

String **OutputHeaderCell** Any number of characters Range Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath Source1Cell String Any number of characters Range Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. Source1Enable Bool Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. String Source1HeaderCell Any number of characters Range Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. Source2Cell String Any number of characters Range Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. Source2Enable Bool Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. Source2HeaderCell String Any number of characters Range Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function.

FileName SpreadsheetFilename Any number of characters Range Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. **Status** String Any number of characters Range Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. WithHeader Bool Description Using ParamEngine = "ExcelParam", Please refer to the corresponding variable for the ExcelMath function. **EXTINCTIONRATIO** app.Measure.Px.Operator (ParamEngine = "ExtinctionRatio") Aperture Double CalcType Enum CursorDisplay Enum **Aperture** Double From 0 to 100 step 0.1 Range Description For eye-diagram parameters which have an "aperture" setting, this defines the region over which the eye digrams vertical information is analyzed. It specifies the percentage of the central region of the eye (relative to 1 Unit Interval) which is used in the analysis. CalcType **Enum** Description Extinction ratio units. **Values**

db linear pct

CursorDi	splay		Enum
Descrip	tion		
Set/	Query the CursorDispla	ay cvar. This defines whether the source trace is annotated with 'Help	
Mari	kers' generated by the	measurement.	
Values			
	Detailed		
	Off		
	Simple		
		EYE	AMPLITUDE
		app.Measure.Px.Operator (ParamEngine =	"EyeAmplitude")
	Aperture	Double	
	CursorDisplay	Enum	
	2 3. 22. 22. 24. 25.		
Aperture			Double
Range	From 0 to 100 step (0.1	
	·		
Descrip			
eye It sp	digrams vertical inform	ers which have an "aperture" setting, this defines the region over which nation is analyzed. The of the central region of the eye (relative to 1 Unit Interval) which is used to 1.	
CursorDi			Enum
Descrip	tion		
Set/		ay cvar. This defines whether the source trace is annotated with 'Help measurement.	
Values			
	Detailed		
	Off		
	Simple		
			AVADOMED
			AVGPOWER
		app.Measure.Px.Operator (ParamEngine =	"EyeAvgPower")
	Aperture	Double	
		,	
Aportura			Doublo
Aperture	-		Double
Range	From 0 to 100 step (J.1	

Description

For eye-diagram parameters which have an "aperture" setting, this defines the region over which the eye digrams vertical information is analyzed.

It specifies the percentage of the central region of the eye (relative to 1 Unit Interval) which is used in the analysis.

EYEBER

app.Measure.Px.Operator (ParamEngine = "EyeBER")

Aperture	Double
CursorDisplay	Enum

Aperture Double

Range From 0 to 100 step 0.1

Description

For eye-diagram parameters which have an "aperture" setting, this defines the region over which the eye digrams vertical information is analyzed.

It specifies the percentage of the central region of the eye (relative to 1 Unit Interval) which is used in the analysis.

Cursor Display Enum

Description

Set/Query the CursorDisplay cvar. This defines whether the source trace is annotated with 'Help Markers' generated by the measurement.

Values

Detailed	
Off	
Simple	

EYECROSSING

app.Measure.Px.Operator (ParamEngine = "EyeCrossing")

Output	Enum
Output	Enum

Output Enum

Description

Type of output returned, percentage of eye height, or absolute voltage.

Values

Absolute	
Percent	

EYEHEIGHT

app.Measure.Px.Operator (ParamEngine = "EyeHeight")

Aperture	Double
CalcUnits	Enum
CursorDisplay	Enum

Aperture Double

Range From 0 to 100 step 0.1

Description

For eye-diagram parameters which have an "aperture" setting, this defines the region over which the eye digrams vertical information is analyzed.

It specifies the percentage of the central region of the eye (relative to 1 Unit Interval) which is used in the analysis.

CalcUnits Enum

Description

Specifies the units of the parameter readout, linear (volts), or decibels.

Values

dB	
linear	

Cursor Display Enum

Description

Set/Query the CursorDisplay cvar. This defines whether the source trace is annotated with 'Help Markers' generated by the measurement.

Values

Detailed	
Off	
Simple	

EYEONELEVEL

app.Measure.Px.Operator (ParamEngine = "EyeOneLevel")

Aperture	Double

Aperture Double

Range From 0 to 100 step 0.1

Description

For eye-diagram parameters which have an "aperture" setting, this defines the region over which the

eye digrams vertical information is analyzed.

It specifies the percentage of the central region of the eye (relative to 1 Unit Interval) which is used in the analysis.

EYEQFACTOR

app.Measure.Px.Operator (ParamEngine = "EyeQFactor")

Aperture	Double
CursorDisplay	Enum

Aperture Double

Range From 0 to 100 step 0.1

Description

For eye-diagram parameters which have an "aperture" setting, this defines the region over which the eye digrams vertical information is analyzed.

It specifies the percentage of the central region of the eye (relative to 1 Unit Interval) which is used in the analysis.

Cursor Display Enum

Description

Set/Query the CursorDisplay cvar. This defines whether the source trace is annotated with 'Help Markers' generated by the measurement.

Values

Detailed	
Off	
Simple	

EYEZEROLEVEL

app.Measure.Px.Operator (ParamEngine = "EyeZeroLevel")

Aperture Double

Aperture Double

Range From 0 to 100 step 0.1

Description

For eye-diagram parameters which have an "aperture" setting, this defines the region over which the eye digrams vertical information is analyzed.

It specifies the percentage of the central region of the eye (relative to 1 Unit Interval) which is used in the analysis.

FALLATLEVEL

app.Measure.Px.Operator (ParamEngine = "FallAtLevel")

HighPct	Double
LevelsAre	Enum
LowPct	Double
SetLevel1090	Action
SetLevel2080	Action

HighPct Double

Range From 10 to 95 step 1

Description

High level in percent.

LevelsAre Enum

Description

Type of level: absolute, percent, %PkPk or %0-Min with EMC option.

Values

Absolute	
Percent	
PercentGNDMin	
PercentPkPk	

LowPct Double

Range From 5 to 90 step 1

Description

High level in percent.

SetLevel1090 Action

Description

Set the levels to 10% and 90% of full amplitude.

SetLevel2080 Action

Description

Set the levels to 20% and 80% of full amplitude.

FASTMULTIWPORT

app.Measure.Px.Operator (ParamEngine = "FastMultiWPort")

AdjustFrame	Bool
ClearCumulative	Bool
ClearSweeps	Action
ForceUpdate	Action

PortName	String
Timeout	Double

AdjustFra	ame	Bool
ClearCun	nulative	Bool
ClearSwe	eeps	Action
Descrip Clea	otion ar any accumulated result data. Useful for example to restart an average, o	r parameter statistics.
ForceUpo	date	Action
PortName Range	e Any number of characters	String
Timeout		Double
Range	From 0 to 100 step 1	

FREQUENCYATLEVEL

app.Measure.Px.Operator (ParamEngine = "FrequencyAtLevel")

FindLevel	Action
Hysteresis	Double
LevelType	Enum
PercentLevel	Double
SignalType	Enum
Slope	Enum
Summary	String

FindLevel	· · · · · · · · · · · · · · · · · · ·	Action
Hysteresi	 \$	Double
Range	From 0 to 10 step 0.1	
LevelType	e	Enum
Values		
	Absolute	
	Percent	
	PercentGNDMax	
	PercentGNDMin	
=	PercentPkPk	

PercentLe	evel					Double
Range	Fror	n 0 to 100 step 1				
SignalTyp	е					Enum
Values						
	Clock	(
	Data					
Slope						Enum
Values						
values						
	Neg Pos					
Summary						String
-	Λον	number of chara	otors			String
Range	Ally	number of chara	ciers			
						GAPWIDTH
				ann Magaura Dy O		
				app.ivieasure.Px.O	perator (ParamEngine	g = Gapvvidiri ,
		AbsLevel1			Double	
		AbsLevel2			Double	
		BitRate			Double	
	•	LevelType			Enum	
		MaxRunLength			Integer	
AbsLevel	1					Double
Range	Fror	n -100 to 100 ste	p 0.0001			
AbsLevel	2					Double
Range	Fror	n -100 to 100 ste	р 0.0001			
BitRate						Double
	Fron	n 0 to 10 1011 oto	n 1000			Double
Range	FIOI	n 0 to 1e+011 ste	ep 1000			
LevelType	•					Enum
Values						
	Abso	lute				
	Perce	ent				
l						

MaxRunLength Integer

Range From 2 to 20 step 1

HALFPERIOD

app.Measure.Px.Operator (ParamEngine = "HalfPeriod")

	1
AbsLevel	Double
FindLevel	Action
Hysteresis	Double
LevelType	Enum
Slope	Enum
Summary	String

AbsLevel		Double
Range	From -100 to 100 step 1e-007	
	tion solute level type is used, then this is the threshold used for transition time detection. Note: the e of this variable setting adapts to the scale of the input signal.	
FindLevel		Action
Hysteresi	s	Double
Range	From 0 to 10 step 0.1	
LevelType)	Enum
Values		
	Absolute	
	Percent	
	PercentGNDMax	
	PercentGNDMin	
	PercentPkPk	
Slope		Enum
Values		
	Both	
	Neg	
	Pos	
Summary		String
Range	Any number of characters	

HOLDTIME

app.Measure.Px.Operator (ParamEngine = "HoldTime")

ClockFindLevel	Action
ClockHysteresis	Double
ClockLevells	Enum
ClockPctLevel	Double
ClockSlope	Enum
DataFindLevel	Action
DataHysteresis	Double
DataLevells	Enum
DataPctLevel	Double
DataSlope	Enum
Summary	String

ClockFindLevel		Action
ClockHys	teresis	Double
Range	From 0 to 10 step 0.1	
ClockLev	ells	Enum
Values		
	Absolute	
	Percent	
	PercentGNDMax	
	PercentGNDMin	
	PercentPkPk	
ClockPctl	Level	Double
Range	From 0 to 100 step 1	
ClockSlop	pe	Enum
Values		
	Both	
	Neg	
	Pos	
DataFindl	Level	Action
DataHysto	eresis	Double
Range	From 0 to 10 step 0.1	

DataLeve	lls	Enum
Values		
	Absolute	
	Percent	
	PercentGNDMax	
•	PercentGNDMin	
	PercentPkPk	
DataPctLe	evel	Double
Range	From 0 to 100 step 1	
DataSlope	•	Enum
Values		
	Both	
	Neg	
	Pos	
Summary		String
Range	Any number of characters	_
		HPARAMSCRIPT app.Measure.Px.Operator (ParamEngine = "HParamScript")
	Code	String
	Language	Enum
	Status	String
	Timeout	Double
Code		String
	Any number of characters	Gum. g
Range	Any number of characters	
Language	•	Enum en la companya de la companya della companya de la companya d
Values		
	JScript	
	VBScript	
Status		String
Range	Any number of characters	

Double **Timeout** From 1 to 12000 step 0.001 Range **LEVELATX** app.Measure.Px.Operator (ParamEngine = "LevelAtX") HorValue Double PinToData Bool TimeFromCvar Bool **HorValue** Double From -1.79769e+308 to 1.79769e+308 step 0 Range Description if the "TimeFromCvar" is set to true, this specifies the horizontal (x) coordinate at which the waveform data "level" or value is to be evaluated **PinToData** Bool Description If set to true, the vertical values are restricted to actual data points, else if false the values can be interpolated (linearly) between points. **TimeFromCvar** Bool Description If true, the horizontal coordinate (typically time) is specified by the "HorValue" cvar, otherwise the time is specified by the input pin. **LOCALBASE** app.Measure.Px.Operator (ParamEngine = "LocalBase") Hysteresis Double Double **Hysteresis** From 0 to 10 step 0.1 Range LOCALBASELINESEPARATION app.Measure.Px.Operator (ParamEngine = "LocalBaselineSeparation")

Hysteresis Double

Hysteresis

Double

Range	From 0 to 10 step 0.1		
		LOCAL	/AXIMUM
		app.Measure.Px.Operator (ParamEngine = "Loc	
	I hostonosio	Davida	
	Hysteresis	Double	
Hysteresis			Double
Range	From 0 to 10 step 0.1		
		LOCAL	MINIMUM
		app.Measure.Px.Operator (ParamEngine = "Loc	calMinimum")
	Hysteresis	Double	
	1,900,000	20000	
Hysteresis			Double
Range	From 0 to 10 step 0.1		
		LOCAL app.Measure.Px.Operator (ParamEngine = "Lo	NUMBER
		appiniededren X.eperator (r dramznyme = 20	y dan van ber y
	Hysteresis	Double	
Hysteresis			Double
Range	From 0 to 10 step 0.1		
		LOCALPEAN app.Measure.Px.Operator (ParamEngine = "LocalP	
		app.ineasure.rx.Operator (raramengine = Locair	eak i or eak)
	Hysteresis	Double	
Hysteresis			Double
Range	From 0 to 10 step 0.1		
		LOCALTIMEAT	/AXIMUM

		app.Measure.Px.Operator (ParamEngine = "LocalTimeAtMaximum")
	Hysteresis	Double
Hysteresis Range	s From 0 to 10 step 0.1	Double
Nange	110111 0 10 10 010 0.1	
		LOCALTIMEATMINIMUM app.Measure.Px.Operator (ParamEngine = "LocalTimeAtMinimum")
	Hysteresis	Double
Hysteresis	 S	Double
Range	From 0 to 10 step 0.1	
		LOCALTIMEBETWEENEVENTS app.Measure.Px.Operator (ParamEngine = "LocalTimeBetweenEvents")
	Hysteresis	Double
Hysteresis	 3	Double
Range	From 0 to 10 step 0.1	
		LOCALTIMEBETWEENPEAKS
		app.Measure.Px.Operator (ParamEngine = "LocalTimeBetweenPeaks")
	Hysteresis	Double
Hysteresis		Double
Range	From 0 to 10 step 0.1	
		LOCALTIMEBETWEENTROUGHS app.Measure.Px.Operator (ParamEngine = "LocalTimeBetweenTroughs")
	Hysteresis	Double

Hysteresis	;			Double
Range	From 0 to 10 step 0.1			
		LOCAI	_TIMEOVERTHR	ESHOLD
		app.Measure.Px.Operator (ParamEng		
	[]	
	Hysteresis Level		Double Double	
Hysteresis	· · · · · · · · · · · · · · · · · · ·			Double
Range	From 0 to 10 step 0.1			
Level				Double
Range	From 0.1 to 100 step 0.01			
		100/	ALTIMEPEAKTO	TROUGH
		app.Measure.Px.Operator (ParamEng		
	Hysteresis		Double	
Llystorosia				Double
Hysteresis Range	From 0 to 10 step 0.1			Double
. 0-	·			
			ALTIMETROUGH	
		app.Measure.Px.Operator (ParamEng	gine = "LocalTimeTrou	ıghToPeak",
	Hysteresis		Double	
Hysteresis	;			Double
Range	From 0 to 10 step 0.1			
		LOCALI	IMEUNDERTHR	ECHOI D
		app.Measure.Px.Operator (ParamEngi		
	Hysteresis		Double	
	Level		Double	

Hysteresis

Range From 0 to 10 step 0.1

Level Double

Range From 0.1 to 100 step 0.01

MATHCADPARAM

app.Measure.Px.Operator (ParamEngine = "MathcadParam")

Advanced	Bool
NewSheet	Bool
OutputEnable	Bool
OutputHeaderVar	String
OutputVar	String
Reload	Action
Source1Enable	Bool
Source1HeaderVar	String
Source1Var	String
Source2Enable	Bool
Source2HeaderVar	String
Source2Var	String
Status	String
WithHeader	Bool
WorksheetFilename	FileName

Advanced

Description

Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the

NewSheet Bool

Description

MathcadMath function.

Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.

OutputEnable Bool

Description

Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.

OutputHeaderVar	String
Range Any number of characters	
Description Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.	
OutputVar	String
Range Any number of characters	
Description Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.	
Reload	Action
Description Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.	
Source1Enable	Bool
Description Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.	
Source1HeaderVar	String
Range Any number of characters	
Description Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.	
Source1Var	String
Range Any number of characters	
Description Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.	
Source2Enable	Bool
Description Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.	
Source2HeaderVar	String
Range Any number of characters	
Description Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.	

Source2Var String

Range Any number of characters

Description

Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.

Status String

Range Any number of characters

Description

Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.

WithHeader Bool

Description

Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.

WorksheetFilename FileName

Range Any number of characters

Description

Using ParamEngine = "MathcadParam", please refer to the corresponding variable for the MathcadMath function.

MATLABPARAMETER

app.Measure.Px.Operator (ParamEngine = "MATLABParameter")

MATLABCode	String
MATLABPlot	Bool

MATLABCode String

Range Any number of characters

Description

String containing the MATLAB code to execute when new data is presented.

MATLABPlot Bool

Description

If true, the result of the MATLAB processing operation is plotted by MATLAB, in a floating window.

MAXIMUM

app.Measure.Px.Operator (ParamEngine = "Maximum")

Calculates the maximum vertical value of the waveform

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
app.Measure.Pl.ParamEngine = "Maximum"
```

MEAN

app.Measure.Px.Operator (ParamEngine = "Mean")

Calculates the mean value of the input waveform's vertical values. When Cyclic = true, the range of values used is limited to a whole number of cycles.

Cyclic Bool

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P1 to mean.
app.Measure.P1.ParamEngine = "Mean"
' Set the mean parameter for cyclic measurements.
app.Measure.P1.Operator.Cyclic = true
```

Cyclic Bool

Description

Sets/Queries whether the mean parameter Px is to be measured over a number of complete cycles.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P2 to mean.
app.Measure.P2.ParamEngine = "Mean"
' Set the mean parameter for cyclic measurements.
app.Measure.P2.ParamEngine.Cyclic = True
```

MEDIAN

app.Measure.Px.Operator (ParamEngine = "Median")

Calculates the median (division between two halves) of the probability distribution of an input waveform. For periodic signals it is advisable to use Cyclic = true.

Cyclic Bool

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
app.Measure.P1.ParamEngine = "Median"
' Set the measurement for a periodic signal
app.Measure.P1.Operator.Cyclic = true
```

Cyclic Bool

Description

Sets/Queries whether the median parameter Px is to be measured over a number of complete cycles.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P2 to median.
app.Measure.P2.ParamEngine = "Median"
' Set the median parameter for cyclic measurements.
app.Measure.P2.Operator.Cyclic = True
```

MINIMUM

app.Measure.Px.Operator (ParamEngine = "Minimum")

Calculates the minimum value of a waveform

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
app.Measure.Pl.ParamEngine = "Minimum"
```

NARROWBANDPHASE

app.Measure.Px.Operator (ParamEngine = "NarrowBandPhase")

Frequency	Double
-----------	--------

Frequency Double

Range From 10 to 4e+010 step 1

NCYCLEJITTER

app.Measure.Px.Operator (ParamEngine = "NCycleJitter")

FindUITime	Bool
N	Integer
UITime	Double
Units	Enum

 Bool

 N
 Integer

 Range
 From 1 to 100000 step 1

 UlTime
 Double

 Range
 From 0 to 1000 step 1e-012

Enum			
			Values
			S
			UI
SITIONSHIFT	NFARTRANS	NONI	
		app.Measure.Px.Operator (ParamEr	
		,, , , , , , , , , , , , , , , , , , , ,	
	Double	PatternDelay	PatternDelay
	Double	PatternLength	PatternLengt
Double			PatternDelay
		om -100 to 100 step 0.01	Range From -100 to 10
Double		 h	PatternLength
		om 1e-009 to 0.001 step 1e-010	Range From 1e-009 to
		om 1e-009 to 0.001 step 1e-010	Range From 1e-009 to
NPOINTS		om 1e-009 to 0.001 step 1e-010	Range From 1e-009 to
	erator (ParamEr	om 1e-009 to 0.001 step 1e-010 app.Measure.Px.O	Range From 1e-009 to
	erator (ParamEr		Range From 1e-009 to
	<i>erator (ParamEr</i> _{Bool}		
		app.Measure.Px.O	
		app.Measure.Px.O	
ingine = "npoints"		app.Measure.Px.O	UsePointsInf
ingine = "npoints"	Bool	app.Measure.Px.O UsePointsInFrame Frame if the returned value is only points inside the displayed frame, or if all	UsePointsInF UsePointsInFrame Description
ingine = "npoints" Bool It are	Bool points in the result	app.Measure.Px.O UsePointsInFrame Frame if the returned value is only points inside the displayed frame, or if all	UsePointsInf UsePointsInFrame Description Choose if the returned
Bool It are	Bool points in the result	app.Measure.Px.O UsePointsInFrame Frame if the returned value is only points inside the displayed frame, or if all	UsePointsInf UsePointsInFrame Description Choose if the returned
Bool It are	Bool points in the result	app.Measure.Px.O	UsePointsInf UsePointsInFrame Description Choose if the returned
Bool It are	Bool Dooints in the result OVERSHOOM The second in the result in the	app.Measure.Px.O	UsePointsInf UsePointsInFrame Description Choose if the returned

app.Measure.Px.C	perator (i	ParamEngine =	= "Overwrite",
	, : - : - :		,

		app.Measure.Px.Operator (ParamEng	
	Frequency	Double	
Frequenc Range	From 10 to 4e+0	10 step 1	Double
		PA app.Measure.Px.Operator (ParamEngine	ARAMSCRIPT = "ParamScript"
	Codo	Chris	
	Code	String Enum	
	Language Status	String	
	Timeout	Double	
Code Range	Any number of c	naracters	String
Language))		Enum
Values	JScript		
	VBScript		
Status Range	Any number of c	naracters	String
Timeout			Double
Range	From 1 to 12000	step 0.001	
		app.Measure.Px.Operator (ParamEngir	PEAKMAG ne = "PEAKMAG",
	FindBaseline	Bool	
FindBase	line		Bool
		Р	EAKTOPEAK

app.Measure.Px.Operator (ParamEngine = "PeakToPeak")

PERCENTILE

app.Measure.Px.Operator (ParamEngine = "Percentile")

HPctPop	Double
PctRes	DoubleLockstep

HPctPop Double

Range From 0 to 100 step 1

Description

Sets/Queries the percentage of the population which falls to the left (or below) the desired percentile. For example, the median is the 50th percentile, or the horizontal coordinate of the histogram at which 50% of the population falls to the left.

PctRes DoubleLockstep

Range From 1e-006 to 1 step 0.01, locked to 1 2 5, fine grain allowed=false, on=false

Description

This control allows you to control the precision or resolution in the percentage. The default is 1%. But you can set the resolution to as low as 1e-6 % (one part in 1e8). This is useful for finding approximate confidence limits.

PERIODATLEVEL

app.Measure.Px.Operator (ParamEngine = "PeriodAtLevel")

FindLevel	Action
Hysteresis	Double
LevelType	Enum
PercentLevel	Double
PFDUpdated	Action
SignalType	Enum
Slope	Enum
Summary	String

FindLevel Action

Hysteresis Double

Range From 0 to 10 step 0.1

LevelType	e				Enum
Values					
	Absolute				
	Percent				
	PercentGNDMax				
	PercentGNDMin				
	PercentPkPk				
PercentLo	evel				Double
Range	From 0 to 100 step	1			
PFDUpda	ited				Action
SignalTyp	ре				Enum
Values					
	Clock				
	Data				
Slope					Enum
Values					
	Neg				
	Pos				
Summary					String
Range	Any number of chara	acters			
					DUACE
			app.Measure.Px.O	perator (ParamEng	PHASE ine = "Phase")
	OutputType			Enum	
	RefFindLevel			Action	
	RefHysteresis			Double	
	RefLevelType			Enum	
	RefPercentLevel			Double	
	RefSlope			Enum	
			-		

RefFindLevel	Action
RefHysteresis	Double
RefLevelType	Enum
RefPercentLevel	Double
RefSlope	Enum
SigFindLevel	Action
SigHysteresis	Double
SigLevelType	Enum
SigPercentLevel	Double
SigSlope	Enum

OutputType Enum

Description

Sets/Queries the output type for Phase Px.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P1 to phase difference.
app.Measure.P1.ParamEngine = "Phase"
' Set the output unit as radians.
app.Measure.P1.Operator.OutputType = "Radians"
```

Values

Degrees	
DEGREES360	
Percent	
Radians	
RADIANSTWOPI	

RefFindLevel Action

Description

Find the test level for the reference trace.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 to phase difference.
app.Measure.P3.ParamEngine = "Phase"
' Find the test level for the reference trace.
app.Measure.P3.Operator.RefFindLevel
```

RefHysteresis Double

Range From 0 to 10 step 0.1

Description

Sets/Queries the hysteresis range for the reference trace.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P1 to phase difference.
app.Measure.P1.ParamEngine = "Phase"
' Set the reference hysteresis in graticule divisions.
app.Measure.P1.Operator.RefHysteresis = 0.7
```

RefLevelType Enum

Description

Sets/Queries the unit of measurement for the test level of the reference trace.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P1 to phase difference.
app.Measure.P1.ParamEngine = "Phase"
' Set the reference level to be measured in absolute units.
app.Measure.P1.Operator.RefLevelType = "Absolute"
```

Values

Absolute	
Percent	
PercentGNDMax	
PercentGNDMin	
PercentPkPk	

RefPercentLevel Double

Range From 0 to 100 step 1

Description

Sets/Queries the test level for the reference trace in percent.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P3 to phase difference.
app.Measure.P3.ParamEngine = "Phase"
' Set the reference test level in percent.
app.Measure.P3.Operator.RefPercentLevel = 55
```

RefSlope Enum

Description

Sets/Queries the polarity of the measured reference transitions.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
' Set parameter P1 to phase difference.
app.Measure.P1.ParamEngine = "Phase"
' Set the reference slope to negative.
app.Measure.P1.Operator.RefSlope = "Neg"
```

Values

Both	
Neg	
Pos	

Action SigFindLevel Description Causes the engine to find a suitable level for either SigLevelType ("Absolute"or "Percent") Double **SigHysteresis** From 0 to 10 step 0.1 Range Description Sets/Queries the hysteresis range for the signal. **Example** ' Visual Basic Script Set app = CreateObject("LeCroy.XStreamDSO") ' Set parameter P3 to phase difference. app.Measure.P3.ParamEngine = "Phase" 'Set the signal hysteresis in graticule divisions. app.Measure.P3.Operator.SigHysteresis = 0.7 SigLevelType Enum Description Sets/Queries which level to use "Percent" or "Absolute" for transitions on the signal **Values** Absolute Percent PercentGNDMax PercentGNDMin PercentPkPk SigPercentLevel Double From 0 to 100 step 1 Range Description Sets/Queries the test level for the signal in percent. **SigSlope** Enum Description Sets/Queries the polarity of the measured signal transitions. **Values** Both Neg Pos

PROTOCOL2ANALOG

app.Measure.Px.Operator (ParamEngine = "Protocol2Analog")

AddressOperator

πυαιεοουμειαιοι	LIIUIII
AddressValue	BitPattern
AddressValue2	BitPattern
FilterType	Enum
FindLevel	Action
Hysteresis	Double
LevelType	Enum
PatternBitLength	Integer
PatternBitPos	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
PercentLevel	Double
Slope	Enum
ViewingMode	Enum

AddressO	perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
AddressV	alue		BitPattern
Range		s=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X lign=BitFix Format=Ehex	
AddressV	alue2		BitPattern
Range		s=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 lign=BitFix Format=Ehex	
FilterType			Enum

FindLevel Action

Values

Any ID IDData

Hysteresi	s	Double
Range	From 0 to 10 step 0.1	
LevelType	•	Enum
Values		
	Absolute	
	Percent	
-	PercentGNDMax	
	PercentGNDMin	
	PercentPkPk	
PatternBi	tLength	Integer
Range	From 1 to 128 step 1	
PatternBi	tPos	Integer
Range	From 0 to 127 step 1	
PatternOp	perator	Enum
Values		
	Equal	
	Greater	
	GreaterOrEqual	
	InRange	
	NotEqual	
	OutRange	
	Smaller	
	SmallerOrEqual	
PatternVa	lue	BitPattern
Range	MaxBits=128 NumBits=8 NumBytes=1 AllowedBitV PadAlign=Left SizeAlign=BitVar Format=Ehex	alues=01X PaddingChar=X
PatternVa	lue2	BitPattern
Range	MaxBits=128 NumBits=8 NumBytes=1 AllowedBitV PadAlign=Left SizeAlign=BitVar Format=Ehex	alues=01 PaddingChar=1
PercentLe	evel	Double
Range	From 0 to 100 step 1	

Slope		Enum
Value	es	
	Both	
	Bothneg	
	Bothpos	
	Neg	
	Pos	
Viewing	Mode	Enum
Value	es	
	Binary	
	Hex	

PROTOCOL2PROTOCOL

app.Measure.Px.Operator (ParamEngine = "Protocol2Protocol")

Protocol1AddressOperator Protocol1AddressValue BitPattern Protocol1AddressValue2 BitPattern Protocol1FilterType Enum Protocol1PatternBitLength Protocol1PatternBitPos Integer Protocol1PatternOperator Enum Protocol1PatternValue BitPattern Protocol1PatternValue2 BitPattern Protocol2AddressOperator Enum Protocol2AddressValue BitPattern Protocol2AddressValue BitPattern Protocol2AddressValue BitPattern Protocol2AddressValue BitPattern Protocol2PatternBitLength Integer Protocol2PatternBitLength Protocol2PatternOperator Enum Protocol2PatternOperator Enum Protocol2PatternValue BitPattern BitPattern Protocol2PatternValue BitPattern Protocol2PatternValue2 BitPattern		
Protocol1AddressValue2 BitPattern Protocol1FilterType Enum Protocol1PatternBitLength Integer Protocol1PatternBitPos Integer Protocol1PatternOperator Enum Protocol1PatternValue BitPattern Protocol1PatternValue2 BitPattern Protocol2AddressOperator Enum Protocol2AddressValue BitPattern Protocol2AddressValue BitPattern Protocol2AddressValue2 BitPattern Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternOperator Enum Protocol2PatternOperator Enum Protocol2PatternValue BitPattern BitPattern Protocol2PatternValue BitPattern	Protocol1AddressOperator	Enum
Protocol1FilterType Enum Protocol1PatternBitLength Integer Protocol1PatternBitPos Integer Protocol1PatternOperator Enum Protocol1PatternValue BitPattern Protocol1PatternValue2 BitPattern Protocol2AddressOperator Enum Protocol2AddressValue BitPattern Protocol2AddressValue BitPattern Protocol2AddressValue2 BitPattern Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternOperator Enum Protocol2PatternValue BitPattern BitPattern BitPattern BitPattern BitPattern BitPattern BitPattern BitPattern BitPattern	Protocol1AddressValue	BitPattern
Protocol1PatternBitLength Integer Protocol1PatternDoperator Enum Protocol1PatternValue BitPattern Protocol1PatternValue2 BitPattern Protocol2AddressOperator Enum Protocol2AddressValue BitPattern Protocol2AddressValue BitPattern Protocol2AddressValue2 BitPattern Protocol2AddressValue2 BitPattern Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternValue BitPattern BitPattern BitPattern BitPattern BitPattern BitPattern BitPattern BitPattern	Protocol1AddressValue2	BitPattern
Protocol1PatternBitPos Integer Protocol1PatternOperator Enum Protocol1PatternValue BitPattern Protocol1PatternValue2 BitPattern Protocol2AddressOperator Enum Protocol2AddressValue BitPattern Protocol2AddressValue2 BitPattern Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternValue BitPattern	Protocol1FilterType	Enum
Protocol1PatternOperator Enum Protocol1PatternValue BitPattern Protocol2PatternValue2 BitPattern Protocol2AddressOperator Enum Protocol2AddressValue BitPattern Protocol2AddressValue2 BitPattern Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternOperator Enum Protocol2PatternOperator Enum Protocol2PatternValue BitPattern BitPattern Enum Protocol2PatternValue BitPattern BitPattern BitPattern BitPattern	Protocol1PatternBitLength	Integer
Protocol1PatternValue BitPattern Protocol2PatternValue2 BitPattern Protocol2AddressOperator Enum Protocol2AddressValue BitPattern Protocol2AddressValue2 BitPattern Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternValue BitPattern	Protocol1PatternBitPos	Integer
Protocol1PatternValue2 Protocol2AddressOperator Enum Protocol2AddressValue BitPattern Protocol2AddressValue2 BitPattern Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternValue BitPattern BitPattern BitPattern BitPos BitPattern BitPattern BitPattern BitPattern BitPattern	Protocol1PatternOperator	Enum
Protocol2AddressOperator Enum Protocol2AddressValue BitPattern Protocol2AddressValue2 BitPattern Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternValue BitPattern Protocol2PatternValue BitPattern	Protocol1PatternValue	BitPattern
Protocol2AddressValue BitPattern Protocol2AddressValue2 BitPattern Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternValue BitPattern Protocol2PatternValue BitPattern	Protocol1PatternValue2	BitPattern
Protocol2AddressValue2 Protocol2FilterType Enum Protocol2PatternBitLength Protocol2PatternBitPos Integer Protocol2PatternOperator Protocol2PatternValue BitPattern BitPattern BitPattern BitPattern	Protocol2AddressOperator	Enum
Protocol2FilterType Enum Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternValue BitPattern Protocol2PatternValue2 BitPattern	Protocol2AddressValue	BitPattern
Protocol2PatternBitLength Integer Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternValue BitPattern Protocol2PatternValue2 BitPattern	Protocol2AddressValue2	BitPattern
Protocol2PatternBitPos Integer Protocol2PatternOperator Enum Protocol2PatternValue BitPattern Protocol2PatternValue2 BitPattern	Protocol2FilterType	Enum
Protocol2PatternOperator Enum Protocol2PatternValue BitPattern Protocol2PatternValue2 BitPattern	Protocol2PatternBitLength	Integer
Protocol2PatternValue BitPattern Protocol2PatternValue2 BitPattern	Protocol2PatternBitPos	Integer
Protocol2PatternValue2 BitPattern	Protocol2PatternOperator	Enum
	Protocol2PatternValue	BitPattern
ViewingMode Enum	Protocol2PatternValue2	BitPattern
	ViewingMode	Enum

Protocol1	AddressOperator	Enum
Values		
	Equal	
	Greater	

GreaterOrEqual

InRange

	SmallerOrEqual	
	Officiality of Equal	
Protocol1	AddressValue	BitPattern
Range	MaxBits=32 NumBits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X PadAlign=Left SizeAlign=BitFix Format=Ehex	
Protocol1	AddressValue2	BitPattern
Range	MaxBits=32 NumBits=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 PadAlign=Left SizeAlign=BitFix Format=Ehex	
Protocol1	FilterType	Enum
Values		
	Any	
	ID .	
	IDData	
Protocol1	PatternBitLength	Integer
Range	From 1 to 128 step 1	
Protocol1	PatternBitPos	
FIOLOCOII	ratternoitros	Integer
Range	From 0 to 127 step 1	Integer
Range		Integer Enum
Range	From 0 to 127 step 1	
Range Protocol1	From 0 to 127 step 1	
Range Protocol1	From 0 to 127 step 1 PatternOperator	
Range Protocol1	PatternOperator Equal	
Range Protocol1	From 0 to 127 step 1 PatternOperator Equal Greater	
Range Protocol1	PatternOperator Equal Greater GreaterOrEqual	
Range Protocol1	From 0 to 127 step 1 PatternOperator Equal Greater GreaterOrEqual InRange NotEqual OutRange	
Range Protocol1	From 0 to 127 step 1 PatternOperator Equal Greater GreaterOrEqual InRange NotEqual OutRange Smaller	
Range Protocol1	From 0 to 127 step 1 PatternOperator Equal Greater GreaterOrEqual InRange NotEqual OutRange	
Range Protocol1 Values	From 0 to 127 step 1 PatternOperator Equal Greater GreaterOrEqual InRange NotEqual OutRange Smaller	
Range Protocol1 Values	From 0 to 127 step 1 PatternOperator Equal Greater GreaterOrEqual InRange NotEqual OutRange Smaller SmallerOrEqual	Enum
Range Protocol1 Values Protocol1 Range	PatternOperator Equal Greater GreaterOrEqual InRange NotEqual OutRange Smaller SmallerOrEqual PatternValue MaxBits=128 NumBits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X	Enum

Protocolz	AddressOperator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
Protocol2	AddressValue		BitPattern
Range		=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X ign=BitFix Format=Ehex	
Protocol2	AddressValue2		BitPattern
Range		=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 ign=BitFix Format=Ehex	
Protocol2	P.FilterType		Enum
Values			
	Any		
	ID		
	IDData		
Protocol2	PatternBitLength		Integer
Range	From 1 to 128 step 1		
Protocol2	PatternBitPos		Integer
Range	From 0 to 127 step 1		
Protocol2	PatternOperator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		

Protocol2	PatternValue		BitPattern
Range		Bits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X Align=BitVar Format=Ehex	
Protocol2	PatternValue2		BitPattern
Range		Bits=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 Align=BitVar Format=Ehex	
/iewingN	lode		Enum
Values			
	Binary		
	Hex		
			_
			COL2VALU
		app.Measure.Px.Operator (ParamEngine =	"Protocol2Valu
	AddressAveles	D'iDatasa	
	AddressValue	BitPattern	
	DefinitionFile	FileName	
	FilterType PatternBitLength	Enum	
	PatternBitPos	Integer Integer	
	ValueCoefficient	Double	
	ValueTerm	Double	
	ValueType	Enum	
	ValueUnit	String	
	ViewingMode	Enum	
AddressV	'alue		BitPattern
Range		its=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X Align=BitFix Format=Ehex	
efinition	File		FileName
Range	Any number of cha	racters	
ilterType)		Enum
Values			
	Any		
	ID		
PatternBi	tl ength		Integer
	From 1 to 128 step		oger

PatternBi	tPns	Integel
		megel
Range	From 0 to 127 step 1	
ValueCoe	fficient	Double
Range	From -1e+050 to 1e+050 step 1e-010	
ValueTerr	n	Double
Range	From -1e+050 to 1e+050 step 1e-010	
ValueTyp	9	Enun
Values		
	Signed	
	Unsigned	
ValueUnit		String
Range	Any number of characters	
ViewingM	ode	Enum
Values		
	Binary	
Į.	Hex	

app.Measure.Px.Operator (ParamEngine = "ProtocolBitrate")

AddressOperator	Enum
AddressValue	BitPattern
AddressValue2	BitPattern
FilterType	Enum
PatternBitLength	Integer
PatternBitPos	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
ViewingMode	Enum

AddressOperator		Enum
Values		
	Equal	
	Greater	

GreaterOrEqual	
InRange	
NotEqual	
OutRange	
Smaller	
SmallerOrEqual	
	1

	OmanciorEqual		
AddressV	'alue		BitPattern
Range		=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X ign=BitFix Format=Ehex	
AddressV	alue2		BitPattern
Range		=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 ign=BitFix Format=Ehex	
FilterType)		Enum
Values			
	Any		
	ID		
	IDData		
PatternBi	tLength		Integer
Range	From 1 to 128 step 1		
PatternBi	tPos		Integer
Range	From 0 to 127 step 1		
PatternOp	perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		

PatternValue BitPattern

Range MaxBits=128 NumBits=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X PadAlign=Left SizeAlign=BitVar Format=Ehex

PatternVa	alue2		BitPattern
Range		its=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 .lign=BitVar Format=Ehex	
ViewingM	lode		Enum
Values			
	Binary		
	Hex		
		PROT app.Measure.Px.Operator (ParamEngine =	OCOLLOAD
	AddressOperator	Enum	
	AddressValue	BitPattern	
	AddressValue2	BitPattern	
	FilterType	Enum	
	PatternBitLength	Integer	
	PatternBitPos	Integer	
	PatternOperator	Enum	
	PatternValue	BitPattern	
	PatternValue2	BitPattern	
	ViewingMode	Enum	
AddressC)perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller SmallerOrEqual		
	SilialieiOiEqual		
AddressV Range		s=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X	BitPattern
Nange		lign=BitFix Format=Ehex	
AddressV	alue2		BitPattern
Range		s=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 lign=BitFix Format=Ehex	

FilterType	e			Enum
Values	.			
	Any			
	ID			
	IDData			
PatternBi	tLength			Integer
Range	From 1 to 128 step 1			
PatternBi	itPos			Integer
Range	From 0 to 127 step 1			
PatternO _l	perator			Enum
Values	1			
	Equal			
	Greater			
	GreaterOrEqual			
	InRange			
	NotEqual			
	OutRange			
	Smaller			
	SmallerOrEqual			
PatternVa	alue			BitPattern
Range		ts=8 NumBytes=1 AllowedBitValues=01X Paddin lign=BitVar Format=Ehex	gChar=X	
PatternVa	alue2			BitPattern
Range		ts=8 NumBytes=1 AllowedBitValues=01 Padding0 lign=BitVar Format=Ehex	Char=1	
ViewingN	lode			Enum
Values				
	Binary			
	Hex			
		PRO app.Measure.Px.Operator (Paramb	OTOCOLNUMN Engine = "ProtocolN	
	AddressOperator		Enum	
	Address\/alug		PitPattorn	

BitPattern

AddressValue2

FilterType	Enum
PatternBitLength	Integer
PatternBitPos	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
ViewingMode	Enum

AddressC	perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
AddressV	/alue		BitPattern
Range		=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X gn=BitFix Format=Ehex	
AddressV	/alue2		BitPattern
Range		=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 gn=BitFix Format=Ehex	
FilterType			Enum
Values			
	Any		
	ID		
	IDData		
PatternBi	tLength		Integer
Range	From 1 to 128 step 1		
PatternBi	tPos		Integer
Range	From 0 to 127 step 1		

PatternOp	erator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
PatternVa	ue		BitPattern
Range		its=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X .lign=BitVar Format=Ehex	
PatternVa	ue2		BitPattern
Range		its=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 .lign=BitVar Format=Ehex	
ViewingM	ode		Enum
Values			
	Binary		
	Hex		
		app.Measure.Px.Operator (ParamEr	PW50 <i>ngine = "PW50")</i>
	Hysteresis	Double	
Hysteresis	 }		Double
Range	From 0 to 10 step 0.	1	
		PW5 app.Measure.Px.Operator (ParamEngine = "	ONEGATIVE PW50Negative")
	Hysteresis	Double	
Hysteresis	;		Double
Range	From 0 to 10 step 0.	1	

PW50POSITIVE

app.Measure.Px.Operator (ParamEngine = "PW50Positive")

Hysteresis Double

Range From 0 to 10 step 0.1

RESOLUTION

app.Measure.Px.Operator (ParamEngine = "Resolution")

Hysteresis	Double

Hysteresis Double

Range From 0 to 10 step 0.1

RISEATLEVEL

app.Measure.Px.Operator (ParamEngine = "RiseAtLevel")

HighPct	Double
LevelsAre	Enum
LowPct	Double
SetLevel1090	Action
SetLevel2080	Action

HighPct Double

Range From 10 to 95 step 1

Description

High level in percent.

Leveisar	е			Enum
Descri	otion			
-		rcent, %PkPk or %0-Min with EMC option.		
Value				
values				
	Absolute			
	Percent			
	PercentGNDMax			
	PercentPkPk			
LowPct				Double
Range	From 5 to 90 step 1			
Descrip	n level in percent.			
SetLevel	1090			Action
Descri	otion			
	the levels to 10% and	90% of full amplitude.		
		<mark>-</mark>		Action
SetLevel	2080			ACTION
Descri	otion			
Set	the levels to 20% and	80% of full amplitude.		
			ROOTMEAN	NSQUARE
		app.Measure.Px.Operator (Pa		-
		177	<u> </u>	
	0 "		5 .	
	Cyclic		Bool	
Cvalia				Bool
Cyclic				Воог
Descri	otion			
If tr	ue, the calculation is lir	nited to a whole number of cycles detected in the in	put.	
				SETUP
		app.Measure.Px.C	perator (ParamEng	
		· ·	· · · · · · · · · · · · · · · · · · ·	
Calculates	the Setup time associ	app.Measure.Px.C	· · · · · · · · · · · · · · · · · · ·	
Calculates	-	· ·	ata.	
Calculates	ClockFindLevel	· ·	· · · · · · · · · · · · · · · · · · ·	
Calculates	-	· ·	ata.	
Calculates	ClockFindLevel ClockHysteresis	· ·	Action Double	
Calculates	ClockFindLevel ClockHysteresis ClockLevelIs	· ·	Action Double Enum	
Calculates	ClockFindLevel ClockHysteresis ClockLevells ClockPctLevel	· ·	Action Double Enum Double	

DataHysteresis	Double
DataLevells	Enum
DataPctLevel	Double
DataSlope	Enum
Summary	String

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
app.Measure.MeasureMode = "MyMeasure"
app.Measure.P1.ParamEngine = "Setup"
```

ClockFindLevel Action

Description

Causes the engine to find a suitable level for either ClockLevells ("Absolute"or "Percent")

ClockHysteresis Double

Range From 0 to 10 step 0.1

Description

Using ParamEngine = "Setup", please refer to the corresponding variable for the Hold Time parameter.

ClockLevells Enum

Description

Sets/Queries whether the Clock signal levels are specified in "Percent" or "Absolute"

Values

Absolute	
Percent	
PercentGNDMax	
PercentGNDMin	
PercentPkPk	

ClockPctLevel Double

Range From 0 to 100 step 1

Description

Using ParamEngine = "Setup", please refer to the corresponding variable for the Hold Time parameter.

ClockSlope Enum

Description

Sets/Queries the polarity of transitions of the Clock signal are used

Values

Both	
Neg	
Pos	

ataFindL	.evel		Action
Descript			
Caus	es the engine to find a	a suitable level for either DataLevells ("Absolute"or	"Percent")
taHyste	eresis		Double
Range	From 0 to 10 step 0.	1	
Descript Using		up", please refer to the corresponding variable for	the Hold Time parameter.
taLevel	ls		Enun
Descript Sets/		Data signal level is DataAbsLevel or DataPctLevel	
Values			
	Absolute		
	Percent		
	PercentGNDMax		
	PercentGNDMin		
	PercentPkPk		
taPctLe	vel		Double
Range	From 0 to 100 step 1		
Usinç ta Slop e	·	up", please refer to the corresponding variable for	the Hold Time parameter. Enum
Descript Sets/		f transitions to be used for the Data signal	
Values			
	Both		
	Neg		
	Pos		
mmary			String
Range	Any number of chara	acters	•
Descript	ion		
_		up", please refer to the corresponding variable for	the Hold Time parameter.
			SKE
		app.Measure.Px.	Operator (ParamEngine = "Ske
		-77	
lculates t	he skew between two	clock signal waveforms	<u> </u>

Clock1Hysteresis	Double
Clock1Levells	Enum
Clock1PctLevel	Double
Clock1Slope	Enum
Clock2FindLevel	Action
Clock2Hysteresis	Double
Clock2Levells	Enum
Clock2PctLevel	Double
Clock2Slope	Enum
Deskew	Double
UpSamplingFactor	Integer

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
app.Measure.MeasureMode = "MyMeasure"
app.Measure.P1.ParamEngine = "Skew"
```

Clock1FindLevel Action

Description

Automatically find a suitable level for Clock1, for either "Percent" or "Absolute" levels

Clock1Hysteresis Double

Range From 0 to 10 step 0.1

Description

Sets/Queries hysteresis for transition detection used for Clock1

Clock1Levells Enum

Description

Sets/Queries whether to use Percent or Absolute levels for Clock1

Values

Absolute	
Percent	
PercentGNDMax	
PercentGNDMin	
PercentPkPk	

Clock1PctLevel Double

Range From 0 to 100 step 1

Description

Sets/Queries the "Percent" of the amplitude of Clock1 to use for a transition level, if Clock1Levells = "Percent"

Clock1SI	ope		Enum
Descrip	otion		
-		f transitions detected on Clock1	
Values			
7 4.4.00	Both		
	Neg		
	Pos		
Clock2Fi	ndLevel		Action
Descrip	ation		
-		ew", please refer to the corresponding variable for the Hold Time parameter	۲.
		,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	
_	ysteresis		Double
Range	From 0 to 10 step 0.	1	
Descrip	otion		
_		r transition detection used for Clock1	
Clock2Le			Enum
Descrip Sets		se Percent or Absolute levels for Clock2	
		SO F GROOM OF A BOOK AS FOR SIGNAL	
Values			
	Absolute		
	Percent		
	PercentGNDMax		
	PercentGNDMin PercentPkPk		
	I GIOGIIII KI K		
Clock2Po	ctLevel		Double
Range	From 0 to 100 step 1		
Descrip	ation		
_		of the amplitude of Clock2 to use for a transition level, if Clock2LevelIs =	
	rcent"	of the amphade of Glock2 to use for a transition level, if Glock2Eevells =	
Clock2SI			Enum
			Liidiii
Descrip			
Sets	s/Queries the polarity o	f transitions detected on Clock2	
Values	5		
	Both		
	Neg		
	Pos		

Deskew
Range From -1e-008 to 1e-008 step 1e-012

UpSamplingFactor
Range From 1 to 20 step 1

SLEW

app.Measure.Px.Operator (ParamEngine = "Slew")

HighPct	Double
LevelsAre	Enum
LowPct	Double
PercentImage	Image
SetLevel1090	Action
SetLevel2080	Action
Slope	Enum

HighPct Double

Range From 40 to 95 step 1

Description

High level in percent.

LevelsAre Enum

Description

Type of level: absolute, percent, %PkPk or %0-Min with EMC option.

Values

Absolute	
Percent	
PercentGNDMax	
PercentPkPk	

LowPct Double

Range From 5 to 60 step 1

Description

High level in percent.

PercentImage Image

SetLevel1090 Action

Description

Set the levels to 10% and 90% of full amplitude.

SetLevel2080			Action	
Descrip Set t		nd 80% of full amplitude.		
Slope			Enum	
Values				
	Neg			
	Pos			
		STANDARDD	EVIATION	
		app.Measure.Px.Operator (ParamEngine = "Stand	lardDeviation")	
	Qualia	Dool		
	Cyclic	Bool		
01			Book	
Cyclic			Bool	
Descrip		limited to a whole number of cycles detected in the input.		
	o, the calculation is	miniou to a whole number of eyelee detected in the input.		
			TAA	
		app.Measure.Px.Operator (ParamEr	ngine = "TAA")	
	Hysteresis	Double		
	1.1/0.00.00.0			
Hysteresi			Double	
Range	From 0 to 10 step	0.1	Double	
Nange				
		TAAI	NEGATIVE	
		app.Measure.Px.Operator (ParamEngine = "T	TAANegative")	
	Hysteresis	Double		
Hysteresi	S		Double	
Range	From 0 to 10 step	0.1		
		TA.	DOCITIVE	
		app.Measure.Px.Operator (ParamEngine = 1	APOSITIVE "TAAPositive")	
	Hustorosis	918500 RevA		

	i iyətci cətə	Ponnie
lveteroci		
-lysteresi	5	
Range	From 0 to 10 step 0.1	

TIE

app.Measure.Px.Operator (ParamEngine = "TIE")

TIE is "Time Interval Error", or the error in expected arrival time of trnasotions in either a data stream or a clock signal. It is the heart of most jitter measurments (where only one signal is under analysis). The Skew processor is closely related to this function in cases where measurements are using a separate reference clock.

WARNING: The TIE processor is appropriate for analysis of "real-time" acquired waveforms for jitter and timing variations. It will give incorrect results for equivalent-time type waveforms.

Annotate	Integer
BaseFrequency	Double
DataIsNRZ	Bool
FindBaseFrequency	Action
FindLevel	Action
FrequencyMultiplier	Double
Hysteresis	Double
IncludeVirtualEdges	Bool
IntervalsEdgeEdge	Integer
IntervalType	Enum
LevelType	Enum
MaxComboIntervals	Integer
PercentLevel	Double
PermitGTHalfUI	Bool
PLL1TransportDelay	Double
PLLCompensateForMissingEdges	Bool
PLLFrequency	Double
PLLType	Enum
SignalType	Enum
Slope	Enum
Summary	String
UseAllEdges	Bool
UseBaseFrequency	Enum
UseMultiEdgeCombos	Bool
UsePLL	Bool
VirtEdgeType	Enum

Annotate Integer

Range From 1 to 10 step 1

BaseFrequency Double

Range From 1 to 2e+012 step 10

Description

This is the frequency of used to provide expected times for TIE. If a PLL is being used, this frequency must be within the capture range for the PLL (usually quite close) or you will encounter unexpected results. Typically the find frequency operation is quite good for setting this value, unless the input source is "data" and the signal is very stressed (closed eye or nearly closed eye).

DataIsNRZ Bool

Description

This should be set to "true" for TIE analysis of an NRZ data stream. It should be set to false for TIE analysis of a clock signal

FindBaseFrequency Action

Description

When activatred starts an automatic process to attempt to learn the base frequency of the clock or data signal (see DatalsNRZ) and set the BaseFrequency contorl to the found value. Warning: be sure to provide as many clock or data cycles as is reasonably possible for maximum precision in the result.

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Automatically find the frequency for clock or data signal at the input of the TIE processor. app.Measure.P3.Operator.FindBaseFrequency

FindLevel Action

Description

Activate this control to find the vertical level for 50% for the waveform presented at the input to this processor. (Only for LevelType = "Absolute"

Example

```
' Visual Basic Script
Set app = CreateObject("LeCroy.XStreamDSO")
```

' Automatically find the level for 50% crossing as an absolute (vertical units) value app.Measure.P3.Operator.FindLevel

FrequencyMultiplier

Double

Range From 0.001 to 1000 step 0.001

Hysteresis Double

Range From 0 to 10 step 0.1

Description

This setting establishes the zone around the level (or threshold for level crossings) which must be traversed by the signal in order for the transition to be "qualified".

Bool IncludeVirtualEdges Description When this control is set to true (default is false), the TIE values the result at the output have "virtual edges" included in the output (i.e. values which are linearly interpolated) corresponding to edges which did NOT transit. This allows a relatively uniform in time strm of values. This feature is mostly obviated by the processor "ParamUpSample" IntervalsEdgeEdge Integer Range From 1 to 100000 step 1 Description For edge-edge methodology, this control sets the number of UI (unit intervals) between edges to be analyzed. IntervalType Enum Description Timing Analysis can either performed using the edge-edge timing methodology (as was developed for Time-Interval-Analyzers", or edge-ref, as is common for real-time oscilloscopes. Edge-Ref is highly recommended. **Values EDGEEDGE EDGEREF** LevelType Enum **Values** Absolute Percent PercentGNDMax PercentGNDMin PercentPkPk **MaxComboIntervals** Integer From 1 to 20000 step 1 Range **PercentLevel** Double From 0 to 100 step 1 Range **PermitGTHalfUI** Bool

PLL1TransportDelay

Range

From 0 to 1 step 1e-015

PLLCompensateForMissingEdges

Double

Bool

PLLFrequ	iency	Double
Range	From 1 to 1e+011 step 100	
PLLType		Enum
Descript	ation	
	mits selection of a PLL type (depending on installed softwa	are options)
1 0111	The colocion of a 1 LE type (depending on motalica control	aro optiono,
Values		
	Custom	
	DVI	
	FBDIMM	
	GOLDEN	
	PCIEXPRESS	
SianolTyn		Enum
SignalTyp	Je	Litani
Values		
raiaes	Clock	
-	Data	
L	Data	
Slope		Enum
Values		
	Both	
	Neg	
	Pos	
Summary		String
-		Sung
Range	Any number of characters	
	ann	Воо
JseAllEdo	ges	B001
JseBaseF	Frequency	Enum
	•	
Values		
	Custom	
F	Standard	
JseMultiE	EdgeCombos	Book
JsePLL		Воог
/irtEdgeT	Гуре	Enum
Values		
value3		
-	Expected	
	Observed	

TIMEATCAN

app.Measure.Px.Operator (ParamEngine = "TimeAtCAN")

DataCondition	Enum
DataValue0	String
DataValue1	String
DataValue2	String
DataValue3	String
DataValue4	String
DataValue5	String
DataValue6	String
DataValue7	String
DLC	Integer
FrameType	Enum
HorValue	Double
ID	String
IDCondition	Enum
ShowBrowseDb	Bool

DataCond	lition		Enum
Values			
	EQ		
	X		
DataValue	e0		String
Range	Any number of chara	acters	
DataValue	e1		String
Range	Any number of chara	acters	
DataValue	e2		String
Range	Any number of chara	acters	
DataValue	e3		String
Range	Any number of chara	acters	
DataValue	e4		String
Range	Any number of chara	acters	
DataValue	e5		String
Range	Any number of chara	acters	

DataValue		
-ata vaide	e 6	String
Range	Any number of characters	
DataValue	27	String
Range	Any number of characters	3
Nange	7 try Hambor of characters	
DLC		Integer
Range	From 0 to 8 step 1	
rameTyp	pe	Enum
Values		
	Data	
	Error	
	Remote	
lorValue		Double
Range	From -1.79769e+308 to 1.79769e+308 step 0	
D		String
Range	Any number of characters	
DConditio	on	Enum
DConditio Values	on	Enum
	DontCare	Enum
		Enum
	DontCare	Enum
	DontCare EQ	Enum
	DontCare EQ GE GT INRANGE	Enum
	DontCare EQ GE GT INRANGE LE	Enum
	DontCare EQ GE GT INRANGE	Enum
Values	DontCare EQ GE GT INRANGE LE LT	Enum
Values	DontCare EQ GE GT INRANGE LE LT	Bool
Values ShowBrow	DontCare EQ GE GT INRANGE LE LT	

	I
FindLevel	Action
Hysteresis	Double
LevelType	Enum
PercentLevel	Double
Slope	Enum
Summary	String

FindLevel			Action
Descrip	tion		
Whe	n in absolute level, find	ds the level at 50%.	
Hysteresi	S		Double
Range	From 0 to 10 step 0.1	1	
Descrip	tion		
-	eresis around level in u	units of divisions.	
LevelType	• · · · · · · · · · · · · · · · · · · ·		Enum
Descrip	tion		
_		cent and %Pkpk, %0-min, %0-max with EMC option.	
Values		Т	
	Absolute		
	Percent PercentGNDMax		
	PercentGNDMin		
	PercentPkPk		
ا - ـ ـ <u></u>		<u></u>	
PercentLe			Double
Range	From 0 to 100 step 1	1	
Descrip	tion		
Leve	l in percent.		
Slope			Enum
Descrip	tion		
_	e of the detected trans	sitions.	
Values			
values	Dath		
	Both		
	Neg Pos		
<u> </u>			
Summary			String
Range	Any number of chara	acters	
Descrip	tion		
Sum	mary of functionality ar	nd settings of processor.	
		TIME	ATPROTOCOL
		app.Measure.Px.Operator (ParamEngine	
		αρμ.ινισαδαιτε.Εχ.Ομεταιοί (ΕαιαπιΕπίβιπε	- IIIII

AddressOperator

Enum

AddressValue	BitPattern
AddressValue2	BitPattern
FilterType	Enum
PatternBitLength	Integer
PatternBitPos	Integer
PatternOperator	Enum
PatternValue	BitPattern
PatternValue2	BitPattern
ViewingMode	Enum

Adaressu	perator		Enum
Values			
	Equal		
	Greater		
	GreaterOrEqual		
	InRange		
	NotEqual		
	OutRange		
	Smaller		
	SmallerOrEqual		
AddressV	'alue		BitPattern
Range		=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X ign=BitFix Format=Ehex	
AddressV	alue2		BitPattern
Range		=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 ign=BitFix Format=Ehex	
FilterType	;		Enum
Values			
	Any		
	ID		
	IDData		
PatternBi	tLength		Integer
Range	From 1 to 128 step 1		
PatternBi	tPos		Integer
Range	From 0 to 127 step 1		

PatternO	perator		Enum	
Values				
	Equal			
	Greater			
	GreaterOrEqual			
	InRange			
	NotEqual			
	OutRange			
	Smaller			
	SmallerOrEqual			
PatternVa	alue		BitPattern	
Range		s=8 NumBytes=1 AllowedBitValues=01X PaddingChar=X ign=BitVar Format=Ehex		
PatternVa	alue2		BitPattern	
Range	Range MaxBits=128 NumBits=8 NumBytes=1 AllowedBitValues=01 PaddingChar=1 PadAlign=Left SizeAlign=BitVar Format=Ehex			
ViewingM	lode		Enum	
Values				
	Binary			
	Hex			
		app.Measure.Px.Operator (Paran	TOP nEngine = "Top")	
		WID ` app.Measure.Px.Operator (ParamEngine =	THATLEVEL : "WidthAtLevel")	
	FindLevel	Action		
	Hysteresis	Double		
	LevelType	Enum		
	PercentLevel	Double		
	Slope	Enum		
	Summary	String		
	- Sammary	Cung		
FindLeve	 I		Action	

Hysteresi	S	Double
Range	From 0 to 10 step 0.1	
LevelType	.	Enum
Values		
	Absolute	
	Percent	
-	PercentGNDMax	
	PercentGNDMin	
	PercentPkPk	
PercentLe	evel	Double
Range	From 0 to 100 step 1	
Slope		Enum
Values		
	Both	
-	Neg	
-	Pos	
Summary		String
		ou mg
Range	Any number of characters	
		XATMAXIMUN
		app.Measure.Px.Operator (ParamEngine = "XAtMaximum"
	HystDiv	Double
	Method	Enum
	Wethou	Liuiii
HystDiv		Double
	From 0.1 to 5 step 0.05	
Range	1 1011 0.1 to 3 step 0.03	
Method		Enum
Values		
	LeftmostMax	
	LocalMaxima	
	RightmostMax	
L	·	

XATMINIMUM

app.Measure.Px.Operator (ParamEngine = "XAtMinimum")

HystDiv	Double
Method	Enum

HystDiv Double

Range From 0.1 to 5 step 0.05

Method Enum

Description

Method to use for finding Minima.

Values

LeftmostMin	
LocalMinima	
RightmostMin	

XATPEAK

app.Measure.Px.Operator (ParamEngine = "XAtPeak")

PeakNumber Integer

PeakNumber Integer

Range From 1 to 10000 step 1

Description

Peak number for which the X value is returned.

Thank you for using Remote Control and Automation on your WaveRunner Oscilloscope.



Corporate Headquarters 700 Chestnut Ridge Road Chestnut Ridge, NY 10977 USA

www.lecroy.com